

globus gass copy

8.6

Generated by Doxygen 1.8.3.1

Thu Nov 7 2013 07:14:51

## Contents

<b>1</b>	<b>Main Page</b>	<b>2</b>
<b>2</b>	<b>Data Structure Index</b>	<b>2</b>
2.1	Data Structures . . . . .	2
<b>3</b>	<b>File Index</b>	<b>2</b>
3.1	File List . . . . .	2
<b>4</b>	<b>Data Structure Documentation</b>	<b>3</b>
4.1	globus_gass_copy_glob_stat_t Struct Reference . . . . .	3
4.1.1	Detailed Description . . . . .	3
4.1.2	Field Documentation . . . . .	3
4.2	globus_gass_copy_state_s Struct Reference . . . . .	3
4.2.1	Detailed Description . . . . .	4
4.2.2	Field Documentation . . . . .	4
4.3	globus_i_gass_copy_buffer_t Struct Reference . . . . .	4
4.3.1	Detailed Description . . . . .	4
4.4	globus_i_gass_copy_cancel_s Struct Reference . . . . .	4
4.4.1	Detailed Description . . . . .	4
4.5	globus_i_gass_copy_monitor_t Struct Reference . . . . .	4
4.5.1	Detailed Description . . . . .	4
4.6	globus_i_gass_copy_state_target_s Struct Reference . . . . .	5
4.6.1	Detailed Description . . . . .	5
4.6.2	Field Documentation . . . . .	5
<b>5</b>	<b>File Documentation</b>	<b>6</b>
5.1	globus_gass_copy.c File Reference . . . . .	6
5.1.1	Detailed Description . . . . .	7
5.1.2	Function Documentation . . . . .	7
5.2	globus_gass_copy.h File Reference . . . . .	19
5.2.1	Detailed Description . . . . .	19
5.2.2	Macro Definition Documentation . . . . .	20
5.2.3	Typedef Documentation . . . . .	20
5.2.4	Enumeration Type Documentation . . . . .	21
5.2.5	Function Documentation . . . . .	21
	<b>Index</b>	<b>22</b>

## 1 Main Page

The Globus GASS Copy library is motivated by the desire to provide a uniform interface to transfer files specified by different protocols. The goals in doing this are to:

- Provide a robust way to describe and apply file transfer properties for a variety of protocols. These include the standard HTTP, FTP and GSIFTP options. Some of the new file transfer capabilities in GSIFTP are parallel, striping, authentication and TCP buffer sizing.
- Provide a service to support nonblocking file transfer and handle asynchronous file and network events.
- Provide a simple and portable way to implement file transfers.

Any program that uses Globus GASS Copy functions must include "globus\_gass\_copy.h".

## 2 Data Structure Index

### 2.1 Data Structures

Here are the data structures with brief descriptions:

<b>globus_gass_copy_glob_stat_t</b> Glob expanded entry information	3
<b>globus_gass_copy_state_s</b> The state structure contains all that is required to perform a file transfer from a source to a destination	3
<b>globus_i_gass_copy_buffer_t</b> The buffer structure used for read/write queue entries	4
<b>globus_i_gass_copy_cancel_s</b> Gass copy cancel struct	4
<b>globus_i_gass_copy_monitor_t</b> The state monitor struct	4
<b>globus_i_gass_copy_state_target_s</b> GASS copy target (e.g	5

## 3 File Index

### 3.1 File List

Here is a list of all documented files with brief descriptions:

<b>globus_gass_copy.c</b> Globus GASS Copy library	6
<b>globus_gass_copy.h</b> Header file for the gass copy library	19

## 4 Data Structure Documentation

### 4.1 globus\_gass\_copy\_glob\_stat\_t Struct Reference

#### Data Fields

- **globus\_gass\_copy\_glob\_entry\_t** type
- char \* **unique\_id**
- char \* **symlink\_target**
- int **mode**
- int **mdtm**
- globus\_off\_t **size**

#### 4.1.1 Detailed Description

Glob expanded entry information.

#### 4.1.2 Field Documentation

##### 4.1.2.1 globus\_gass\_copy\_glob\_entry\_t globus\_gass\_copy\_glob\_stat\_t::type

The file type of the entry.

##### 4.1.2.2 char\* globus\_gass\_copy\_glob\_stat\_t::unique\_id

A string that uniquely identifies the data that the entry refers to.

A file and a symlink to that file will have the same unique\_id. It is NULL for when not available.

##### 4.1.2.3 char\* globus\_gass\_copy\_glob\_stat\_t::symlink\_target

This points to the full path of the target of a symlink.

It is NULL for non-symlinks or when not available.

##### 4.1.2.4 int globus\_gass\_copy\_glob\_stat\_t::mode

An integer specifying the mode of the file.

It is set to -1 when not available.

##### 4.1.2.5 int globus\_gass\_copy\_glob\_stat\_t::mdtm

An integer specifying the modification time of the file.

It is set to -1 when not available.

##### 4.1.2.6 globus\_off\_t globus\_gass\_copy\_glob\_stat\_t::size

A globus\_off\_t specifying the size of the file.

It is set to -1 when not available.

### 4.2 globus\_gass\_copy\_state\_s Struct Reference

## Data Fields

- **globus\_i\_gass\_copy\_target\_t** **source**
- **globus\_i\_gass\_copy\_target\_t** **dest**
- **globus\_i\_gass\_copy\_monitor\_t** **monitor**
- **globus\_mutex\_t** **mutex**
- **globus\_i\_gass\_copy\_cancel\_status\_t** **cancel**

### 4.2.1 Detailed Description

The state structure contains all that is required to perform a file transfer from a source to a destination.

### 4.2.2 Field Documentation

#### 4.2.2.1 **globus\_i\_gass\_copy\_target\_t** **globus\_gass\_copy\_state\_s::source**

Source information for the file transfer.

#### 4.2.2.2 **globus\_i\_gass\_copy\_target\_t** **globus\_gass\_copy\_state\_s::dest**

Dest information for the file transfer.

#### 4.2.2.3 **globus\_i\_gass\_copy\_monitor\_t** **globus\_gass\_copy\_state\_s::monitor**

Used for signalling from the various callback functions.

#### 4.2.2.4 **globus\_mutex\_t** **globus\_gass\_copy\_state\_s::mutex**

coordinates the modifying of the state, aside from the target structures

#### 4.2.2.5 **globus\_i\_gass\_copy\_cancel\_status\_t** **globus\_gass\_copy\_state\_s::cancel**

indicates the status of the cancel operation.

## 4.3 **globus\_i\_gass\_copy\_buffer\_t** Struct Reference

### 4.3.1 Detailed Description

The buffer structure used for read/write queue entries.

## 4.4 **globus\_i\_gass\_copy\_cancel\_s** Struct Reference

### 4.4.1 Detailed Description

gass copy cancel struct

## 4.5 **globus\_i\_gass\_copy\_monitor\_t** Struct Reference

### 4.5.1 Detailed Description

The state monitor struct.

## 4.6 globus\_i\_gass\_copy\_state\_target\_s Struct Reference

### Data Fields

- char \* **url**
- globus\_gass\_copy\_attr\_t \* **attr**
- globus\_mutex\_t **mutex**
- globus\_fifo\_t **queue**
- int **n\_pending**
- int **n\_simultaneous**
- int **n\_complete**
- globus\_i\_gass\_copy\_target\_status\_t **status**
- globus\_gass\_copy\_url\_mode\_t **mode**
- globus\_gass\_transfer\_request\_t **request**
- globus\_bool\_t **free\_handle**
- globus\_bool\_t **seekable**

### 4.6.1 Detailed Description

GASS copy target (e.g. source, destination) transfer information.

### 4.6.2 Field Documentation

#### 4.6.2.1 char\* globus\_i\_gass\_copy\_state\_target\_s::url

url for file transfer

#### 4.6.2.2 globus\_gass\_copy\_attr\_t\* globus\_i\_gass\_copy\_state\_target\_s::attr

attributes to control file transfer

#### 4.6.2.3 globus\_mutex\_t globus\_i\_gass\_copy\_state\_target\_s::mutex

coordinates the modifying of the target structure

#### 4.6.2.4 globus\_fifo\_t globus\_i\_gass\_copy\_state\_target\_s::queue

a queue to manage the reading/writing of data buffers

#### 4.6.2.5 int globus\_i\_gass\_copy\_state\_target\_s::n\_pending

Used for keeping track of reads/writes in the read/write queue.

#### 4.6.2.6 int globus\_i\_gass\_copy\_state\_target\_s::n\_simultaneous

Used to limit the number of n\_pending.

#### 4.6.2.7 int globus\_i\_gass\_copy\_state\_target\_s::n\_complete

Used to compute the offset for ftp writes.

#### 4.6.2.8 globus\_i\_gass\_copy\_target\_status\_t globus\_i\_gass\_copy\_state\_target\_s::status

signifies the target has been successfully setup

#### 4.6.2.9 `globus_gass_copy_url_mode_t` `globus_i_gass_copy_state_target_s::mode`

mode used to identify the below target union struct.

#### 4.6.2.10 `globus_gass_transfer_request_t` `globus_i_gass_copy_state_target_s::request`

GASS equivalent of a handle.

#### 4.6.2.11 `globus_bool_t` `globus_i_gass_copy_state_target_s::free_handle`

If the IO handle was passed as an argument then FALSE If the IO handle was created internally then TRUE.

#### 4.6.2.12 `globus_bool_t` `globus_i_gass_copy_state_target_s::seekable`

Can `globus_io_file_seek()` be performed on this handle?

## 5 File Documentation

### 5.1 `globus_gass_copy.c` File Reference

#### Functions

- `globus_result_t` **`globus_gass_copy_handle_init`** (`globus_gass_copy_handle_t` \*handle, `globus_gass_copy_handleattr_t` \*attr)
- `globus_result_t` **`globus_gass_copy_handle_destroy`** (`globus_gass_copy_handle_t` \*handle)
- `globus_result_t` **`globus_gass_copy_set_buffer_length`** (`globus_gass_copy_handle_t` \*handle, int length)
- `globus_result_t` **`globus_gass_copy_get_buffer_length`** (`globus_gass_copy_handle_t` \*handle, int \*length)
- `globus_result_t` **`globus_gass_copy_set_no_third_party_transfers`** (`globus_gass_copy_handle_t` \*handle, `globus_bool_t` no\_third\_party\_transfers)
- `globus_result_t` **`globus_gass_copy_get_no_third_party_transfers`** (`globus_gass_copy_handle_t` \*handle, `globus_bool_t` \*no\_third\_party\_transfers)
- `globus_result_t` **`globus_gass_copy_set_allocate`** (`globus_gass_copy_handle_t` \*handle, `globus_bool_t` send\_allo)
- `globus_result_t` **`globus_gass_copy_set_stat_on_expand`** (`globus_gass_copy_handle_t` \*handle, `globus_bool_t` always\_stat)
- `globus_result_t` **`globus_gass_copy_set_partial_offsets`** (`globus_gass_copy_handle_t` \*handle, `globus_off_t` offset, `globus_off_t` end\_offset)
- `globus_result_t` **`globus_gass_copy_get_partial_offsets`** (`globus_gass_copy_handle_t` \*handle, `globus_off_t` \*offset, `globus_off_t` \*end\_offset)
- `globus_result_t` **`globus_gass_copy_attr_init`** (`globus_gass_copy_attr_t` \*attr)
- `globus_result_t` **`globus_gass_copy_attr_set_ftp`** (`globus_gass_copy_attr_t` \*attr, `globus_ftp_client_operationattr_t` \*ftp\_attr)
- `globus_result_t` **`globus_gass_copy_attr_set_io`** (`globus_gass_copy_attr_t` \*attr, `globus_io_attr_t` \*io\_attr)
- `globus_result_t` **`globus_gass_copy_attr_set_gass`** (`globus_gass_copy_attr_t` \*attr, `globus_gass_transfer_requestattr_t` \*gass\_attr)
- `globus_result_t` **`globus_gass_copy_get_url_mode`** (char \*url, `globus_gass_copy_url_mode_t` \*mode)
- `globus_result_t` **`globus_gass_copy_register_performance_cb`** (`globus_gass_copy_handle_t` \*handle, **`globus_gass_copy_performance_cb_t`** callback, void \*user\_arg)
- `globus_result_t` **`globus_gass_copy_get_status`** (`globus_gass_copy_handle_t` \*handle, `globus_gass_copy_status_t` \*status)
- const char \* **`globus_gass_copy_get_status_string`** (`globus_gass_copy_handle_t` \*handle)
- `globus_result_t` **`globus_gass_copy_url_to_url`** (`globus_gass_copy_handle_t` \*handle, char \*source\_url, `globus_gass_copy_attr_t` \*source\_attr, char \*dest\_url, `globus_gass_copy_attr_t` \*dest\_attr)

- globus\_result\_t **globus\_gass\_copy\_url\_to\_handle** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, globus\_io\_handle\_t \*dest\_handle)
- globus\_result\_t **globus\_gass\_copy\_handle\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, globus\_io\_handle\_t \*source\_handle, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr)
- globus\_result\_t **globus\_gass\_copy\_register\_url\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_register\_url\_to\_handle** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, globus\_io\_handle\_t \*dest\_handle, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_register\_handle\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, globus\_io\_handle\_t \*source\_handle, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_cache\_url\_state** (globus\_gass\_copy\_handle\_t \*handle, char \*url)
- globus\_result\_t **globus\_gass\_copy\_flush\_url\_state** (globus\_gass\_copy\_handle\_t \*handle, char \*url)
- globus\_result\_t **globus\_gass\_copy\_set\_user\_pointer** (globus\_gass\_copy\_handle\_t \*handle, void \*user\_pointer)
- globus\_result\_t **globus\_gass\_copy\_get\_user\_pointer** (globus\_gass\_copy\_handle\_t \*handle, void \*\*user\_data)
- globus\_result\_t **globus\_gass\_copy\_cancel** (globus\_gass\_copy\_handle\_t \*handle, globus\_gass\_copy\_callback\_t cancel\_callback, void \*cancel\_callback\_arg)
- globus\_result\_t **globus\_i\_gass\_copy\_target\_cancel** (globus\_i\_gass\_copy\_cancel\_t \*cancel\_info)

### 5.1.1 Detailed Description

Globus GASS Copy library.

#### See Also

See the detailed description in **globus\_gass\_copy.h** (p. 19)

### 5.1.2 Function Documentation

#### 5.1.2.1 globus\_result\_t globus\_gass\_copy\_handle\_init ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_gass\_copy\_handleattr\_t \* *attr* )

Initialize a GASS Copy handle.

A globus\_gass\_copy\_handle must be initialized before any transfers may be associated with it. This function initializes a globus\_gass\_copy\_handle to be used for doing transfers, this includes initializing a globus\_ftp\_client\_handle which will be used for doing any ftp/gsiftp transfers. The same handle may be used to perform multiple, consecutive transfers. However, there can only be one transfer associated with a particular handle at any given time. After all transfers to be associated with this handle have completed, the handle should be destroyed by calling **globus\_gass\_copy\_handle\_destroy()** (p. 8).

#### Parameters

<i>handle</i>	The handle to be initialized
<i>attr</i>	The handle attributes used to use with this handle

#### Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.



#### See Also

**globus\_gass\_copy\_handle\_destroy()** (p. 8) , **globus\_gass\_copy\_handleattr\_init()**, **globus\_ftp\_client\_handle\_init()**

References GLOBUS\_GASS\_COPY\_MODULE.

#### 5.1.2.2 globus\_result\_t globus\_gass\_copy\_handle\_destroy ( globus\_gass\_copy\_handle\_t \* *handle* )

Destroy a GASS Copy handle.

Destroy a **gass\_copy\_handle**, which was initialized using **globus\_gass\_copy\_handle\_init()** (p. 7), that will no longer be used for doing transfers. Once the handle is destroyed, no further transfers should be associated with it.

#### Parameters

<i>handle</i>	The handle to be destroyed
---------------	----------------------------

#### Returns

This function returns GLOBUS\_SUCCESS if successful, or a **globus\_result\_t** indicating the error that occurred.

#### See Also

**globus\_gass\_copy\_handle\_init()** (p. 7), **globus\_ftp\_client\_handle\_destroy()**

References GLOBUS\_GASS\_COPY\_MODULE.

#### 5.1.2.3 globus\_result\_t globus\_gass\_copy\_set\_buffer\_length ( globus\_gass\_copy\_handle\_t \* *handle*, int *length* )

Set the size of the buffer to be used for doing transfers.

This function allows the user to set the size of the buffer that will be used for doing transfers, if this function is not called the buffer size will default to 1M.

#### Parameters

<i>handle</i>	Set the buffer length for transfers associated with this handle.
<i>length</i>	The length, in bytes, to make the buffer.

#### Returns

This function returns GLOBUS\_SUCCESS if successful, or a **globus\_result\_t** indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

#### 5.1.2.4 globus\_result\_t globus\_gass\_copy\_get\_buffer\_length ( globus\_gass\_copy\_handle\_t \* *handle*, int \* *length* )

Get the size of the buffer being used for doing transfers.

This function allows the user to get the size of the buffer that is being used for doing transfers.

#### Parameters

<i>handle</i>	Get the buffer length for transfers associated with this handle.
<i>length</i>	The length, in bytes, of the buffer.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.5** globus\_result\_t globus\_gass\_copy\_set\_no\_third\_party\_transfers ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t *no\_third\_party\_transfers* )

Turn third-party transfers on or off.

(They are on by default.)

This function allows the user to turn third-party transfers on or off for ftp to ftp transfers associated with a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

## Parameters

<i>handle</i>	Turn third-party transfers on or off for transfers associated with this handle. They are on by default.
<i>no_third_party_transfers</i>	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References globus\_gass\_copy\_get\_status(), and GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.6** globus\_result\_t globus\_gass\_copy\_get\_no\_third\_party\_transfers ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t \* *no\_third\_party\_transfers* )

See if third-party transfers are turned on or off.

(They are on by default.)

This function allows the user to see if third-party transfers are turned on or off for ftp to ftp transfers associated with a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

## Parameters

<i>handle</i>	See if third-party transfers are turned on or off for transfers associated with this handle. They are on by default.
<i>no_third_party_transfers</i>	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.7 globus\_result\_t globus\_gass\_copy\_set\_allocate ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t *send\_allo* )

Set allo on or off.

5.1.2.8 globus\_result\_t globus\_gass\_copy\_set\_stat\_on\_expand ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t *always\_stat* )

Make globus\_gass\_copy\_expand\_url() always send stat info.

5.1.2.9 globus\_result\_t globus\_gass\_copy\_set\_partial\_offsets ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_off\_t *offset*, globus\_off\_t *end\_offset* )

Set the offsets to be used for doing partial transfers.

This function allows the user to set the offsets that will be used for doing partial transfers. An offset of -1 will disable partial transfers. An end\_offset of -1 means EOF.

## Parameters

<i>handle</i>	Set the offsets for partial transfers associated with this handle.
<i>offset</i>	The starting offset for the partial transfer.
<i>end_offset</i>	The ending offset for the partial transfer.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.10 globus\_result\_t globus\_gass\_copy\_get\_partial\_offsets ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_off\_t \* *offset*, globus\_off\_t \* *end\_offset* )

Get the offsets being used for doing partial transfers.

This function allows the user to get the offsets that are being used for doing partial transfers. An offset of -1 means partial transfers are disabled.

## Parameters

<i>handle</i>	Get the offsets for partial transfers associated with this handle.
<i>offset</i>	The starting offset for the partial transfer.
<i>end_offset</i>	The ending offset for the partial transfer.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.11 globus\_result\_t globus\_gass\_copy\_attr\_init ( globus\_gass\_copy\_attr\_t \* *attr* )

Initialize an attribute structure.

The `globus_gass_copy_attr_t` can be used to pass the `globus_gass_copy` library information about how a transfer should be performed. It must first be initialized by calling this function. Then any or all of the following functions may be called to set attributes associated with a particular protocol: **`globus_gass_copy_attr_set_ftp()`** (p. 11), **`globus_gass_copy_attr_set_gass()`** (p. 12), **`globus_gass_copy_attr_set_io()`** (p. 11). Any function which takes a `globus_gass_copy_attr_t` as an argument will also accept `GLOBUS_NULL`, in which case the appropriate set of default attributes will be used.

#### Parameters

<i>attr</i>	The attribute structure to be initialized
-------------	---

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

#### See Also

**`globus_gass_copy_attr_set_ftp()`** (p. 11), **`globus_gass_copy_attr_set_gass()`** (p. 12), **`globus_gass_copy_attr_set_io()`** (p. 11), **`globus_gass_copy_get_url_mode()`** (p. 12).

References `GLOBUS_GASS_COPY_MODULE`.

**5.1.2.12 `globus_result_t globus_gass_copy_attr_set_ftp ( globus_gass_copy_attr_t * attr, globus_ftp_client_operationattr_t * ftp_attr )`**

Set the attributes for ftp/gsiftp transfers.

In order to specify attributes for ftp/gsiftp transfers, a `globus_ftp_client_operationattr_t` should be initialized and its values set using the appropriate `globus_ftp_client_operationattr_*` functions. The `globus_ftp_client_operationattr_t *` can then be passed to the `globus_gass_copy_attr_t` via this function.

#### Parameters

<i>attr</i>	A <code>globus_gass_copy</code> attribute structure
<i>ftp_attr</i>	The ftp/gsiftp attributes to be used

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

#### See Also

**`globus_gass_copy_attr_init()`** (p. 10), **`globus_gass_copy_attr_set_gass()`** (p. 12), **`globus_gass_copy_attr_set_io()`** (p. 11), **`globus_gass_copy_get_url_mode()`** (p. 12), `globus_ftp_client_operationattr_*`

References `GLOBUS_GASS_COPY_MODULE`.

**5.1.2.13 `globus_result_t globus_gass_copy_attr_set_io ( globus_gass_copy_attr_t * attr, globus_io_attr_t * io_attr )`**

Set the attributes for file transfers.

In order to specify attributes for file transfers, a `globus_io_attr_t` should be initialized and its values set using the appropriate `globus_io_attr_*` functions. The `globus_io_attr_t` can then be passed to the `globus_gass_copy_attr_t` via this function.

#### Parameters

<i>attr</i>	A <code>globus_gass_copy</code> attribute structure
<i>io_attr</i>	The file attributes to be used

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See Also

**globus\_gass\_copy\_attr\_init()** (p. 10), **globus\_gass\_copy\_attr\_set\_gass()** (p. 12), **globus\_gass\_copy\_attr\_set\_ftp()** (p. 11), **globus\_gass\_copy\_get\_url\_mode()** (p. 12), globus\_io\_attr\_\*

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.14 globus\_result\_t globus\_gass\_copy\_attr\_set\_gass ( globus\_gass\_copy\_attr\_t \* attr, globus\_gass\_transfer\_requestattr\_t \* gass\_attr )**

Set the attributes for http/https transfers.

In order to specify attributes for http/https transfers, a globus\_gass\_transfer\_requestattr\_t should be initialized and its values set using the appropriate globus\_gass\_transfer\_requestattr\_\* functions. The globus\_gass\_transfer\_requestattr\_t can then be passed to the globus\_gass\_copy\_attr\_t via this function.

## Parameters

<i>attr</i>	A globus_gass_copy attribute structure
<i>gass_attr</i>	The http/https attributes to be used

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See Also

**globus\_gass\_copy\_attr\_init()** (p. 10), **globus\_gass\_copy\_attr\_set\_io()** (p. 11), **globus\_gass\_copy\_attr\_set\_ftp()** (p. 11), **globus\_gass\_copy\_get\_url\_mode()** (p. 12), globus\_gass\_transfer\_requestattr\_\*

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.15 globus\_result\_t globus\_gass\_copy\_get\_url\_mode ( char \* url, globus\_gass\_copy\_url\_mode\_t \* mode )**

Classify the URL schema into the transfer method that will be used to do the actual tranfer.

This function enables the user to determine what protocol will be used to transfer data to/from a particular url. This information can then be used to specify the appropriate attributes when initiating a transfer.

## Parameters

<i>url</i>	The URL for schema checking
<i>mode</i>	the filled in schema type of the URL param

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See Also

**globus\_gass\_copy\_attr\_init()** (p. 10), **globus\_gass\_copy\_attr\_set\_io()** (p. 11), **globus\_gass\_copy\_attr\_set\_ftp()** (p. 11), globus\_gass\_copy\_set\_gass()

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.16 `globus_result_t globus_gass_copy_register_performance_cb ( globus_gass_copy_handle_t * handle, globus_gass_copy_performance_cb_t callback, void * user_arg )`

Register a performance information callback.

Use this to register a performance information callback. You change or set to GLOBUS\_NULL the callback any time a transfer is not occurring.

#### Parameters

<i>handle</i>	an initialized gass copy handle for which you would like to see performance info
<i>callback</i>	the performance callback
<i>user_arg</i>	a user pointer that will be passed to all callbacks for a given handle

#### Returns

- GLOBUS\_SUCCESS
- error on a NULL or busy handle

#### See Also

**globus\_gass\_copy\_performance\_cb\_t** (p. 20)

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.17 `globus_result_t globus_gass_copy_get_status ( globus_gass_copy_handle_t * handle, globus_gass_copy_status_t * status )`

Get the status code of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLOBUS\_GASS\_COPY\_STATUS\_NONE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_SUCCESS, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_FAILURE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_CANCELLED

#### Parameters

<i>handle</i>	A globus_gass_copy_handle
<i>status</i>	Will be one of the following: GLOBUS_GASS_COPY_STATUS_NONE (No transfers have been initiated using this handle.) GLOBUS_GASS_COPY_STATUS_PENDING (A transfer is currently being set up.) GLOBUS_GASS_COPY_STATUS_TRANSFER_IN_PROGRESS (There is currently a transfer in progress.) GLOBUS_GASS_COPY_STATUS_CANCEL (The last transfer initiated using this handle has been cancelled by the user before completing, and is in the process of being cleaned up.) GLOBUS_GASS_COPY_STATUS_FAILURE (The last transfer initiated using this handle failed, and is in the process of being cleaned up.) GLOBUS_GASS_COPY_STATUS_DONE_SUCCESS (The last transfer initiated using this handle has completed successfully.) GLOBUS_GASS_COPY_STATUS_DONE_FAILURE (The last transfer initiated using this handle failed and has finished cleaning up.) GLOBUS_GASS_COPY_STATUS_DONE_CANCELLED (The last transfer initiated using this handle was cancelled and has finished cleaning up.)

#### Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

#### 5.1.2.18 `const char* globus_gass_copy_get_status_string ( globus_gass_copy_handle_t * handle )`

Get the status string of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLOBUS\_GASS\_COPY\_STATUS\_NONE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_SUCCESS, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_FAILURE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_CANCELLED

##### Parameters

<i>handle</i>	A <code>globus_gass_copy_handle</code>
---------------	--

##### Returns

Returns a pointer to a character string describing the current status

References `globus_gass_copy_get_status()`.

#### 5.1.2.19 `globus_result_t globus_gass_copy_url_to_url ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, char * dest_url, globus_gass_copy_attr_t * dest_attr )`

Transfer data from source URL to destination URL (blocking)

##### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer from the source should be done
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done

##### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

##### Return values

<code>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</code>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<code>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</code>	next error description

##### See Also

`globus_gass_copy_url_to_handle()` (p. 14) `globus_gass_copy_handle_to_url()` (p. 15)

References GLOBUS\_GASS\_COPY\_MODULE, and `globus_gass_copy_register_url_to_url()`.

#### 5.1.2.20 `globus_result_t globus_gass_copy_url_to_handle ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, globus_io_handle_t * dest_handle )`

Transfer data from source URL to an IO handle (blocking)

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer from the source should be done
<i>dest_handle</i>	transfer data to this IO handle

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

#### See Also

**globus\_gass\_copy\_url\_to\_url()** (p. 14) **globus\_gass\_copy\_handle\_to\_url()** (p. 15)

References GLOBUS\_GASS\_COPY\_MODULE, and globus\_gass\_copy\_register\_url\_to\_handle().

5.1.2.21 **globus\_result\_t globus\_gass\_copy\_handle\_to\_url ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_io\_handle\_t \* *source\_handle*, char \* *dest\_url*, globus\_gass\_copy\_attr\_t \* *dest\_attr* )**

Transfer data from an IO handle to destination URL (blocking)

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_handle</i>	transfer data from this IO handle
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description



See Also

**globus\_gass\_copy\_url\_to\_url()** (p. 14) **globus\_gass\_copy\_url\_to\_handle()** (p. 14)

References GLOBUS\_GASS\_COPY\_MODULE, and globus\_gass\_copy\_register\_handle\_to\_url().

**5.1.2.22** `globus_result_t globus_gass_copy_register_url_to_url ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, char * dest_url, globus_gass_copy_attr_t * dest_attr, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from source URL to destination URL (non-blocking)

This functions initiates a transfer from source URL to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer form the source should be done
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the <code>callback_func</code> .

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<code>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</code>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<code>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</code>	next error description

See Also

**globus\_gass\_copy\_register\_url\_to\_handle()** (p. 16), **globus\_gass\_copy\_register\_handle\_to\_url()** (p. 17)

References globus\_i\_gass\_copy\_state\_target\_s::attr, globus\_gass\_copy\_state\_s::cancel, globus\_gass\_copy\_state\_s::dest, globus\_gass\_copy\_get\_url\_mode(), GLOBUS\_GASS\_COPY\_MODULE, and globus\_gass\_copy\_state\_s::source.

**5.1.2.23** `globus_result_t globus_gass_copy_register_url_to_handle ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, globus_io_handle_t * dest_handle, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from source URL to an IO handle (non-blocking)

This functions initiates a transfer from source URL to an IO handle, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer from the source should be done
<i>dest_handle</i>	transfer data to this IO handle
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the callback_func.

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

#### See Also

**globus\_gass\_copy\_register\_url\_to\_url()** (p. 16), **globus\_gass\_copy\_register\_handle\_to\_url()** (p. 17)

References `globus_gass_copy_state_s::cancel`, `globus_gass_copy_state_s::dest`, `globus_gass_copy_get_url_mode()`, `GLOBUS_GASS_COPY_MODULE`, and `globus_gass_copy_state_s::source`.

**5.1.2.24** `globus_result_t globus_gass_copy_register_handle_to_url ( globus_gass_copy_handle_t * handle, globus_io_handle_t * source_handle, char * dest_url, globus_gass_copy_attr_t * dest_attr, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from an IO handle to destination URL (non-blocking)

This functions initiates a transfer from an IO handle to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_handle</i>	transfer data from this IO handle
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the callback_func.

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

#### See Also

**globus\_gass\_copy\_register\_url\_to\_url()** (p. 16), **globus\_gass\_copy\_register\_url\_to\_handle()** (p. 16)

References `globus_gass_copy_state_s::cancel`, `globus_gass_copy_state_s::dest`, `globus_gass_copy_get_url_mode()`, `GLOBUS_GASS_COPY_MODULE`, and `globus_gass_copy_state_s::source`.

#### 5.1.2.25 `globus_result_t globus_gass_copy_cache_url_state ( globus_gass_copy_handle_t * handle, char * url )`

Cache connections to an FTP or GSIFTP server.

Explicitly cache connections to URL server. When an URL is cached, the connection to the URL server will not be closed after a file transfer completes.

#### Parameters

<i>handle</i>	Handle which will contain a cached connection to the URL server.
<i>url</i>	The URL of the FTP or GSIFTP server to cache.

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

References `GLOBUS_GASS_COPY_MODULE`.

#### 5.1.2.26 `globus_result_t globus_gass_copy_flush_url_state ( globus_gass_copy_handle_t * handle, char * url )`

Remove a cached connection to an FTP or GSIFTP server.

Explicitly remove a cached connection to an FTP or GSIFTP server. If an idle connection to an FTP server exists, it will be closed.

#### Parameters

<i>handle</i>	Handle which contains a cached connection to the URL server.
<i>url</i>	The URL of the FTP or GSIFTP server to remove.

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

References `GLOBUS_GASS_COPY_MODULE`.

#### 5.1.2.27 `globus_result_t globus_gass_copy_set_user_pointer ( globus_gass_copy_handle_t * handle, void * user_pointer )`

Set a pointer in the handle to point at user-allocated memory.

References `GLOBUS_GASS_COPY_MODULE`.

**5.1.2.28** `globus_result_t globus_gass_copy_get_user_pointer ( globus_gass_copy_handle_t * handle, void ** user_data )`

Get the pointer in the handle that points to user-allocated memory.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.29** `globus_result_t globus_gass_copy_cancel ( globus_gass_copy_handle_t * handle, globus_gass_copy_callback_t cancel_callback, void * cancel_callback_arg )`

Cancel the current transfer associated with this handle,.

store the `cancel_callback` and `cancel_callback_arg` in the handle. Needed because the ftp callback will be the one given from the original `globus_ftp_client_third_party_transfer()` call.

References GLOBUS\_GASS\_COPY\_MODULE, and `globus_l_gass_copy_target_cancel()`.

**5.1.2.30** `globus_result_t globus_l_gass_copy_target_cancel ( globus_i_gass_copy_cancel_t * cancel_info )`

Cancel the source or destination transfer in progress.

References GLOBUS\_GASS\_COPY\_MODULE, `globus_i_gass_copy_state_target_s::mode`, and `globus_i_gass_copy_state_target_s::url`.

## 5.2 globus\_gass\_copy.h File Reference

### Data Structures

- struct **globus\_gass\_copy\_glob\_stat\_t**

### Macros

- #define **GLOBUS\_GASS\_COPY\_MODULE** (&globus\_i\_gass\_copy\_module)

### Typedefs

- typedef void(\* **globus\_gass\_copy\_performance\_cb\_t** )(void \**user\_arg*, globus\_gass\_copy\_handle\_t \**handle*, globus\_off\_t *total\_bytes*, float *instantaneous\_throughput*, float *avg\_throughput*)
- typedef void(\* **globus\_gass\_copy\_glob\_entry\_cb\_t** )(const char \**url*, const **globus\_gass\_copy\_glob\_stat\_t** \**info\_stat*, void \**user\_arg*)

### Enumerations

- enum **globus\_gass\_copy\_glob\_entry\_t**

### Functions

- `globus_result_t globus_gass_copy_glob_expand_url (globus_gass_copy_handle_t *handle, const char *url, globus_gass_copy_attr_t *attr, globus_gass_copy_glob_entry_cb_t entry_cb, void *user_arg)`
- `globus_result_t globus_gass_copy_mkdir (globus_gass_copy_handle_t *handle, char *url, globus_gass_copy_attr_t *attr)`

#### 5.2.1 Detailed Description

Header file for the gass copy library.

## 5.2.2 Macro Definition Documentation

### 5.2.2.1 #define GLOBUS\_GASS\_COPY\_MODULE (&globus\_i\_gass\_copy\_module)

Module descriptor.

Globus GASS Copy uses standard Globus module activation and deactivation. Before any Globus GASS Copy functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GASS_COPY_MODULE)
```

This function returns GLOBUS\_SUCCESS if Globus GASS Copy was successfully initialized, and you are therefore allowed to subsequently call Globus GASS Copy functions. Otherwise, an error code is returned, and Globus GASS Copy functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GASS Copy, the following function must be called:

```
globus_module_deactivate(GLOBUS_GASS_COPY_MODULE)
```

This function should be called once for each time Globus GASS Copy was activated.

## 5.2.3 Typedef Documentation

### 5.2.3.1 typedef void(\* globus\_gass\_copy\_performance\_cb\_t)(void \*user\_arg, globus\_gass\_copy\_handle\_t \*handle, globus\_off\_t total\_bytes, float instantaneous\_throughput, float avg\_throughput)

Gass copy transfer performance callback.

This callback is registered with 'globus\_gass\_copy\_register\_performance\_cb'. It will be called during a transfer to supply performance information on current transfer. Its frequency will be at most one per second, but it is possible to receive no callbacks. This is possible in very short transfers and in ftp transfers in which the server does not provide performance information.

#### Parameters

<i>handle</i>	the gass copy handle this transfer is occurring on
<i>user_arg</i>	a user pointer registered with 'globus_gass_copy_register_performance_cb'
<i>total_bytes</i>	the total number of bytes transfer so far
<i>instantaneous_throughput</i>	instantaneous rate of transfer (since last callback or start) (bytes / sec)
<i>avg_throughput</i>	the avg throughput calculated since the start of the transfer (bytes / sec)

#### Returns

- n/a

### 5.2.3.2 typedef void(\* globus\_gass\_copy\_glob\_entry\_cb\_t)(const char \*url, const globus\_gass\_copy\_glob\_stat\_t \*info\_stat, void \*user\_arg)

Gass copy glob entry callback.

This callback is passed as a parameter to **globus\_gass\_copy\_glob\_expand\_url()** (p. 21). It is called once for each entry that the original expands to.

#### Parameters

<i>url</i>	The full url to the expanded entry. A directory entry will end in a forward slash '/'.
<i>stat</i>	A pointer to a <b>globus_gass_copy_glob_stat_t</b> (p. 3) containing information about the entry.
<i>user_arg</i>	The <i>user_arg</i> passed to <code>globus_gass_copy_glob_expand()</code>

#### See Also

**globus\_gass\_copy\_glob\_stat\_t** (p. 3), **globus\_gass\_copy\_glob\_expand\_url** (p. 21)

### 5.2.4 Enumeration Type Documentation

#### 5.2.4.1 enum globus\_gass\_copy\_glob\_entry\_t

globbed entry types

### 5.2.5 Function Documentation

#### 5.2.5.1 globus\_result\_t globus\_gass\_copy\_glob\_expand\_url ( globus\_gass\_copy\_handle\_t \* *handle*, const char \* *url*, globus\_gass\_copy\_attr\_t \* *attr*, globus\_gass\_copy\_glob\_entry\_cb\_t *entry\_cb*, void \* *user\_arg* )

Expand globbed url.

This function expands wildcards in a globbed url, and calls `entry_cb()` on each one.

#### Parameters

<i>handle</i>	A gass copy handle to use for the operation.
<i>url</i>	The URL to expand. The URL may be an ftp, gsiftp or file URL. Wildcard characters supported are '?' '*' '[' ']' in the filename portion of the url.
<i>attr</i>	Gass copy attributes for this operation.
<i>entry_cb</i>	Function to call with information about each entry
<i>user_arg</i>	An argument to pass to <code>entry_cb()</code>

#### Returns

This function returns an error when any of these conditions are true:

- *handle* is GLOBUS\_NULL
- *url* is GLOBUS\_NULL
- *url* cannot be parsed
- *url* is not a ftp, gsiftp or file url

References `globus_gass_copy_glob_expand_url()`, GLOBUS\_GASS\_COPY\_MODULE, `globus_gass_copy_glob_stat_t::mdtm`, `globus_gass_copy_glob_stat_t::mode`, `globus_gass_copy_glob_stat_t::size`, `globus_gass_copy_glob_stat_t::symlink_target`, `globus_gass_copy_glob_stat_t::type`, and `globus_gass_copy_glob_stat_t::unique_id`.

#### 5.2.5.2 globus\_result\_t globus\_gass\_copy\_mkdir ( globus\_gass\_copy\_handle\_t \* *handle*, char \* *url*, globus\_gass\_copy\_attr\_t \* *attr* )

Make directory.

This function creates a directory given a ftp or file url.

#### Parameters

<i>handle</i>	A gass copy handle to use for the mkdir operation.
<i>url</i>	The URL for the directory to create. The URL may be an ftp, gsiftp or file URL.
<i>attr</i>	Gass copy attributes for this operation.

#### Returns

This function returns an error when any of these conditions are true:

- *handle* is GLOBUS\_NULL
- *url* is GLOBUS\_NULL
- *url* cannot be parsed
- *url* is not a ftp, gsiftp or file url
- the directory could not be created

References `globus_gass_copy_get_url_mode()`, `globus_gass_copy_mkdir()`, and GLOBUS\_GASS\_COPY\_MODULE.

## Index

attr  
    globus\_i\_gass\_copy\_state\_target\_s, 4

cancel  
    globus\_gass\_copy\_state\_s, 3

dest  
    globus\_gass\_copy\_state\_s, 3

free\_handle  
    globus\_i\_gass\_copy\_state\_target\_s, 5

GLOBUS\_GASS\_COPY\_MODULE  
    globus\_gass\_copy.h, 18

globus\_gass\_copy.c, 5  
    globus\_gass\_copy\_attr\_init, 9  
    globus\_gass\_copy\_attr\_set\_ftp, 10  
    globus\_gass\_copy\_attr\_set\_gass, 11  
    globus\_gass\_copy\_attr\_set\_io, 10  
    globus\_gass\_copy\_cache\_url\_state, 17  
    globus\_gass\_copy\_cancel, 17  
    globus\_gass\_copy\_flush\_url\_state, 17  
    globus\_gass\_copy\_get\_buffer\_length, 7  
    globus\_gass\_copy\_get\_no\_third\_party\_transfers,  
        8  
    globus\_gass\_copy\_get\_partial\_offsets, 9  
    globus\_gass\_copy\_get\_status, 12  
    globus\_gass\_copy\_get\_status\_string, 12  
    globus\_gass\_copy\_get\_url\_mode, 11  
    globus\_gass\_copy\_get\_user\_pointer, 17  
    globus\_gass\_copy\_handle\_destroy, 7  
    globus\_gass\_copy\_handle\_init, 6  
    globus\_gass\_copy\_handle\_to\_url, 14  
    globus\_gass\_copy\_register\_handle\_to\_url, 16  
    globus\_gass\_copy\_register\_performance\_cb, 11  
    globus\_gass\_copy\_register\_url\_to\_handle, 15  
    globus\_gass\_copy\_register\_url\_to\_url, 14  
    globus\_gass\_copy\_set\_allocate, 8  
    globus\_gass\_copy\_set\_buffer\_length, 7  
    globus\_gass\_copy\_set\_no\_third\_party\_transfers,  
        8  
    globus\_gass\_copy\_set\_partial\_offsets, 9  
    globus\_gass\_copy\_set\_stat\_on\_expand, 9  
    globus\_gass\_copy\_set\_user\_pointer, 17  
    globus\_gass\_copy\_url\_to\_handle, 13  
    globus\_gass\_copy\_url\_to\_url, 13  
    globus\_l\_gass\_copy\_target\_cancel, 18

globus\_gass\_copy.h, 18  
    GLOBUS\_GASS\_COPY\_MODULE, 18  
    globus\_gass\_copy\_glob\_entry\_cb\_t, 19  
    globus\_gass\_copy\_glob\_entry\_t, 20  
    globus\_gass\_copy\_glob\_expand\_url, 20  
    globus\_gass\_copy\_mkdir, 20  
        globus\_gass\_copy\_performance\_cb\_t, 19  
    globus\_gass\_copy\_attr\_init  
        globus\_gass\_copy.c, 9  
    globus\_gass\_copy\_attr\_set\_ftp  
        globus\_gass\_copy.c, 10  
    globus\_gass\_copy\_attr\_set\_gass  
        globus\_gass\_copy.c, 11  
    globus\_gass\_copy\_attr\_set\_io  
        globus\_gass\_copy.c, 10  
    globus\_gass\_copy\_cache\_url\_state  
        globus\_gass\_copy.c, 17  
    globus\_gass\_copy\_cancel  
        globus\_gass\_copy.c, 17  
    globus\_gass\_copy\_flush\_url\_state  
        globus\_gass\_copy.c, 17  
    globus\_gass\_copy\_get\_buffer\_length  
        globus\_gass\_copy.c, 7  
    globus\_gass\_copy\_get\_no\_third\_party\_transfers  
        globus\_gass\_copy.c, 8  
    globus\_gass\_copy\_get\_partial\_offsets  
        globus\_gass\_copy.c, 9  
    globus\_gass\_copy\_get\_status  
        globus\_gass\_copy.c, 12  
    globus\_gass\_copy\_get\_status\_string  
        globus\_gass\_copy.c, 12  
    globus\_gass\_copy\_get\_url\_mode  
        globus\_gass\_copy.c, 11  
    globus\_gass\_copy\_get\_user\_pointer  
        globus\_gass\_copy.c, 17  
    globus\_gass\_copy\_glob\_entry\_cb\_t  
        globus\_gass\_copy.h, 19  
    globus\_gass\_copy\_glob\_entry\_t  
        globus\_gass\_copy.h, 20  
    globus\_gass\_copy\_glob\_expand\_url  
        globus\_gass\_copy.h, 20  
    globus\_gass\_copy\_glob\_stat\_t, 2  
        mdtm, 2  
        mode, 2  
        size, 2  
        symlink\_target, 2  
        type, 2  
        unique\_id, 2  
    globus\_gass\_copy\_handle\_destroy  
        globus\_gass\_copy.c, 7  
    globus\_gass\_copy\_handle\_init  
        globus\_gass\_copy.c, 6  
    globus\_gass\_copy\_handle\_to\_url  
        globus\_gass\_copy.c, 14  
    globus\_gass\_copy\_mkdir  
        globus\_gass\_copy.h, 20  
    globus\_gass\_copy\_performance\_cb\_t  
        globus\_gass\_copy.h, 19



```

globus_gass_copy_register_handle_to_url
    globus_gass_copy.c, 16
globus_gass_copy_register_performance_cb
    globus_gass_copy.c, 11
globus_gass_copy_register_url_to_handle
    globus_gass_copy.c, 15
globus_gass_copy_register_url_to_url
    globus_gass_copy.c, 14
globus_gass_copy_set_allocate
    globus_gass_copy.c, 8
globus_gass_copy_set_buffer_length
    globus_gass_copy.c, 7
globus_gass_copy_set_no_third_party_transfers
    globus_gass_copy.c, 8
globus_gass_copy_set_partial_offsets
    globus_gass_copy.c, 9
globus_gass_copy_set_stat_on_expand
    globus_gass_copy.c, 9
globus_gass_copy_set_user_pointer
    globus_gass_copy.c, 17
globus_gass_copy_state_s, 3
    cancel, 3
    dest, 3
    monitor, 3
    mutex, 3
    source, 3
globus_gass_copy_url_to_handle
    globus_gass_copy.c, 13
globus_gass_copy_url_to_url
    globus_gass_copy.c, 13
globus_i_gass_copy_buffer_t, 3
globus_i_gass_copy_cancel_s, 3
globus_i_gass_copy_monitor_t, 3
globus_i_gass_copy_state_target_s, 4
    attr, 4
    free_handle, 5
    mode, 5
    mutex, 4
    n_complete, 4
    n_pending, 4
    n_simultaneous, 4
    queue, 4
    request, 5
    seekable, 5
    status, 5
    url, 4
globus_l_gass_copy_target_cancel
    globus_gass_copy.c, 18

mdtm
    globus_gass_copy_glob_stat_t, 2
mode
    globus_gass_copy_glob_stat_t, 2
    globus_i_gass_copy_state_target_s, 5
monitor
    globus_gass_copy_state_s, 3

mutex
    globus_gass_copy_state_s, 3
    globus_i_gass_copy_state_target_s, 4

n_complete
    globus_i_gass_copy_state_target_s, 4
n_pending
    globus_i_gass_copy_state_target_s, 4
n_simultaneous
    globus_i_gass_copy_state_target_s, 4

queue
    globus_i_gass_copy_state_target_s, 4

request
    globus_i_gass_copy_state_target_s, 5

seekable
    globus_i_gass_copy_state_target_s, 5
size
    globus_gass_copy_glob_stat_t, 2
source
    globus_gass_copy_state_s, 3
status
    globus_i_gass_copy_state_target_s, 5
symlink_target
    globus_gass_copy_glob_stat_t, 2

type
    globus_gass_copy_glob_stat_t, 2

unique_id
    globus_gass_copy_glob_stat_t, 2
url
    globus_i_gass_copy_state_target_s, 4

```