

SCORE-P USER MANUAL

1.3 (revision 7349)

Fri Aug 29 2014 14:42:08

COPYRIGHT ©2009-2012,

RWTH Aachen University, Germany
Gesellschaft fuer numerische Simulation mbH, Germany
Technische Universitaet Dresden, Germany
University of Oregon, Eugene, USA
Forschungszentrum Juelich GmbH, Germany
German Research School for Simulation Sciences GmbH, Germany
Technische Universitaet Muenchen, Germany

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

* Neither the names of

RWTH Aachen University,
Gesellschaft fuer numerische Simulation mbH Braunschweig,
Technische Universitaet Dresden,
University of Oregon, Eugene,
Forschungszentrum Juelich GmbH,
German Research School for Simulation Sciences GmbH, or the
Technische Universitaet Muenchen,

nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Contents

	Page
Contents	iii
1 Introduction	1
1.1 About this Document	2
1.2 Getting Help and Support	3
1.3 Basics of Performance Optimization	3
1.4 Score-P Software Architecture Overview	5
1.5 Acknowledgment	8
2 Getting Started	9
2.1 Score-P Quick Installation	9
2.1.1 Prerequisites	10
2.1.2 General Autotools Build Options	10
2.1.3 Score-P Specific Build Options	11
2.2 Instrumentation	12
2.3 Measurement and Analysis	14
2.4 Report Examination	14
2.5 Simple Example	15
3 Application Instrumentation	17
3.1 Automatic Compiler Instrumentation	22
3.2 Manual Region Instrumentation	23
3.3 Instrumentation for Parameter-Based Profiling	26
3.4 Measurement Control Instrumentation	27
3.5 Source-Code Instrumentation Enabling Online Access	28
3.6 Semi-Automatic Instrumentation of POMP2 User Regions	29
3.7 Preprocessing before POMP2 and OpenMP instrumentation	31
3.8 Source-Code Instrumentation Using PDT	31
3.8.1 Limitations	32
3.9 Binary Instrumentation Using Cobi	32
3.10 Enforce Linking of Static/Shared Score-P Libraries	33
4 Application Measurement	35
4.1 Profiling	36

CONTENTS

4.1.1	Parameter-Based Profiling	37
4.1.2	Phase Profiling	37
4.1.3	Dynamic Region Profiling	37
4.1.4	Clustering	39
4.1.5	Enabling additional debug output on inconsistent profiles	40
4.2	Tracing	41
4.3	Filtering	41
4.3.1	Source File Name Filter Block	42
4.3.2	Region Name Filter Block	43
4.4	Selective Recording	44
4.5	Trace Buffer Rewind	46
4.5.1	Selection of MPI Groups	47
4.6	Recording MPI Communicator Names	49
4.7	Recording Performance Metrics	49
4.7.1	PAPI Hardware Performance Counters	49
4.7.2	Resource Usage Counters	50
4.7.3	Metric Plugins	51
4.8	CUDA Performance Measurement	52
4.9	Online Access Interface	53
5	Usage of scorep-score	57
5.1	Basic usage	57
5.2	Additional per-region information	59
5.3	Defining and testing a filter	59
5.4	Calculating the effects of recording hardware counters	60
6	Performance Analysis Workflow Using Score-P	61
6.1	Program Instrumentation	62
6.2	Summary Measurement Collection	63
6.3	Summary report examination	64
6.4	Summary experiment scoring	64
6.5	Advanced summary measurement collection	66
6.6	Advanced summary report examination	68
6.7	Event trace collection and examination	69
Appendix A	Score-P INSTALL	73
Appendix B	MPI wrapper affiliation	89
B.1	Function to group	89
B.2	Group to function	97
Appendix C	Score-P Metric Plugin Example	103
Appendix D	Score-P Tools	107
D.1	scorep	107

CONTENTS

D.2	scorep-config	109
D.3	scorep-info	110
D.4	scorep-score	110
D.5	scorep-backend-info	111
Appendix E Score-P Measurement Configuration Variables		113
Appendix F Module Documentation		123
F.1	Score-P User Adapter	123
F.1.1	Detailed Description	125
F.1.2	Define Documentation	125
Appendix G File Documentation		153
G.1	SCOREP_User.h File Reference	153
G.1.1	Detailed Description	154
G.2	SCOREP_User_Types.h File Reference	154
G.2.1	Detailed Description	155
G.2.2	Define Documentation	155
G.2.3	Typedef Documentation	156

Chapter 1

Introduction

This document provides an introduction to [Score-P](#): the *Scalable Performance Measurement Infrastructure for Parallel Codes*. It is a software system that provides a measurement infrastructure for profiling, event trace recording, and online analysis of High Performance Computing (HPC) applications. It has been developed within the framework of the Scalable Infrastructure for the Automated Performance Analysis of Parallel Codes ([SILC](#)) project funded by the German Federal Ministry of Education and Research ([BMBF](#)) under its HPC programme and the Performance Refactoring of Instrumentation, Measurement, and Analysis Technologies for Petascale Computing ([PRIMA](#)) project, funded by the United States Department of Energy ([DOE](#)) with the goals of being highly scalable and easy to use.

The partners involved in the development of this system within the SILC and PRIMA projects were:

- [Forschungszentrum Jülich](#),
- [German Research School for Simulation Sciences](#),
- [Gesellschaft für numerische Simulation mbH](#),
- [Gesellschaft für Wissens- und Technologietransfer der TU Dresden \(GWT-TUD GmbH\)](#),
- [Rheinisch-Westfälische Technische Hochschule \(RWTH\) Aachen](#),
- [Technische Universität Dresden](#),
- [Technische Universität München](#),
- and [University of Oregon](#)

The goal of Score-P is to simplify the analysis of the behavior of high performance computing software and to allow the developers of such software to find out where and why performance problems arise, where bottlenecks may be expected and where their codes offer room for further improvements with respect to the run time. A number of tools have been around to help in this respect, but typically each of these tools has only handled a certain subset of the questions of interest. A software developer who wanted to have a complete picture of his code therefore was required to use a multitude of programs to obtain the desired information. Most of these utilities work along similar principles. The first step is usually an instrumentation of the code to be investigated. Next, the instrumented programs are executed and write out (often very large amounts of) performance data. These data are then finally graphically displayed and analyzed after the end of the program run. In certain special cases, the visualization and analysis of the program behavior is also done while the program is running.

A crucial problem in the traditional approach used to be the fact that each analysis tool had its own instrumentation system, so the user was commonly forced to repeat the instrumentation procedure if more than one tool was to be employed. In this context, Score-P offers the user a maximum of convenience by providing the Opari2 instrumenter as a common infrastructure for a number of analysis tools like [Periscope](#), [Scalasca](#), [Vampir](#), and [Tau](#) that obviates the need for multiple repetitions of the instrumentation and thus substantially reduces the amount of work required. It is open for other tools as well. Moreover, Score-P provides the new Open Trace Format Version 2 (OTF2) for the tracing data and the new CUBE4 profiling data format which allow a better scaling of the tools with respect to both the run time of the process to be analyzed and the number of cores to be used.

@scorep supports the following programming paradigms:

- Multi-process paradigms:** • *MPI*
 - *SHMEM*
- Thread-parallel paradigms:** • *OpenMP*
 - *Pthreads*
- Accelerator-based paradigms:** • *CUDA*

And possible combinations from these including simple *serial* programs.

1.1 About this Document

This document consists of three parts. This chapter is devoted to a basic introduction to performance analysis in general and the components of the Score-P system in particular. Chapter [2](#) is a beginner's guide to using the Score-P tool suite.

1.2 Getting Help and Support

It demonstrates the basic steps and commands required to initiate a performance analysis of a parallel application. In the Chapters 3 and 4, the reader can find more detailed information about the components of Score-P. Chapter 6 provides a typical workflow of performance analysis with Score-P and detailed instructions.

1.2 Getting Help and Support

The Score-P project uses various mailing lists to coordinate the development and to provide support to the user community. An overview of the available mailing lists can be found in 1.1.

You can subscribe to the news@score-p.org and support@score-p.org by ...

Table 1.1: Score-P mailing lists

List Address	Subscription	Posting	Usage
news@score-p.org	open	core team	Important news regarding the Score-P software, e.g. announcements of new releases.
support@score-p.org	closed	anyone	Bug reports and general user support for the Score-P software.

1.3 Basics of Performance Optimization

Performance optimization is a process that is usually executed in a work cycle consisting of a number of individual steps as indicated in Figure 1.1.

Thus, the process always begins with the original application in its unoptimized state. This application needs to be instrumented, i. e. it must be prepared in order to enable the measurement of the performance properties to take place. There are different ways to do this, including manual instrumentation of the source code by the user, automatic instrumentation by the compiler, or linking against pre-instrumented libraries. All these options are available in Score-P.

When the instrumented application obtained in this way is executed, the additional commands introduced during the instrumentation phase collect the data required to evaluate the performance properties of the code. Depending on the user's requirements, Score-P allows to store these data either as a profile or as event traces. The user must keep in mind here that the execution of the additional instructions of course requires some run time and storage space. Thus the measurement itself




Figure 1.1: The performance optimization cycle

has a certain influence of the performance of the instrumented code. Whether the perturbations introduced in this way have a significant effect on the behavior depends on the specific structure of the code to be investigated. In many cases the perturbations will be rather small so that the overall results can be considered to be a realistic approximation of the corresponding properties of the uninstrumented code. However, certain constructions like regions with very small temporal extent that are executed frequently are likely to suffer from significant perturbations. It is therefore advisable not to measure such regions.

The next step is the analysis of the data obtained in the measurement phase. Traditionally this has mainly been done post mortem, i. e. after the execution of the instrumented application has ended. This is of course possible in Score-P too, but Score-P offers the additional option to go into the analysis in the so-called on-line mode, i. e. to investigate the performance data while the application is still running. If the collected data are event traces then a more detailed investigation is possible than in the case of profiles. In particular, one can then also look at more sophisticated dependencies between events happening on different processes.

The optimization cycle then continues with the presentation of the analysis results in a report. Here it is important to eliminate the part of the information that is irrelevant for the code optimization from the measured data. The reduction of the complexity achieved in this way will simplify the evaluation of the data for the user. However, care must be taken in order not to present the results in a too abstract fashion which would hide important facts from the user.

1.4 Score-P Software Architecture Overview

The performance report then allows the user to evaluate the performance of the code. One can then either conclude that the application behaves sufficiently well and exit the optimization cycle with the optimized version of the software being chosen as the final state, or one can proceed to identify weaknesses that need to be addressed and the potential for improvements of the code.

In the latter case, one then continues by changing the source code according to the outcome of the previous step and thus obtains an improved application that then can again be instrumented to become ready for a re-entry into the optimization cycle.

1.4 Score-P Software Architecture Overview

In order to allow the user to perform such an optimization of his code (typically written in Fortran, C, or C++ and implemented in a serial way or using a parallelization via an multi-process, thread-parallel, accelerator-based paradigm, or a combination thereof), the Score-P system provides a number of components that interact with each other and with external tools. A graphical overview of this structure is given in Fig. 1.2. We shall now briefly introduce the elements of this structure; more details will be given in the later chapters of this document.




Figure 1.2: Overview of the Score-P measurement system architecture and the tools interface.

In order to instrument an application, the user needs to recompile the application using the Score-P instrumentation command, which is added as a prefix to the original compile and link command lines. It automatically detects the programming paradigm by parsing the original build instructions and utilizes appropriate and configurable methods of instrumentation. These are currently:

- compiler instrumentation,
- MPI and SHMEM library interposition,
- source code instrumentation via the TAU instrumenter,
- OpenMP source code instrumentation using Opari2.
- Pthread instrumentation via GNU ld library wrapping.
- binary instrumentation using Cobi
- CUDA instrumentation

While the first three of these methods are based on using tools provided externally, the Opari2 instrumenter for OpenMP programs is a part of the Score-P infrastructure itself. It is an extension of the well known and frequently used [OpenMP Pragma And Region Instrumenter](#) system (Opari) that has been successfully used in the past in combination with tools like Scalasca, VampirTrace and ompP. The fundamental concept of such a system is a source-to-source translation that automatically adds all necessary calls to a runtime measurement library allowing to collect runtime performance data of Fortran, C, or C++ OpenMP applications. This translation is based on the idea of OpenMP pragma/directive rewriting. The key innovation in Opari2, as compared to its predecessor, is the capability to support features introduced in version 3.0 of the OpenMP standard, in particular its new tasking functionality and OpenMP nesting. Opari used to work by automatically wrapping OpenMP constructs like parallel regions with calls to the portable OpenMP monitoring interface [POMP](#). In order to reflect the above-mentioned extensions, this interface also had to be replaced by an enhanced version, POMP2.

Additionally, the user may instrument the code manually with convenient macros provided by Score-P. Score-P also includes the option for instrumentation of executables using binary rewriting. Later Score-P may be extended with sampling functionality that provides an alternative to direct instrumentation.

During measurement, the system records several performance metrics including execution time, communication metrics, and optionally hardware counters. Performance data is stored in appropriately sized chunks of a preallocated memory buffer that are assigned to threads on demand, efficiently utilizing the available memory and avoiding measurement perturbation by flushing the data to disk prematurely.

1.4 Score-P Software Architecture Overview

Without recompilation, measurement runs can switch between *tracing* and *profiling* mode. In tracing mode, the performance events are passed to the tracing back-end of Score-P and are written to files for subsequent post mortem analysis using Scalasca or Vampir. This backend uses the newly developed Open Trace Format 2 (OTF2), the joint successor of the [Open Trace Format](#) used by Vampir and the Epilog format used by Scalasca. The Score-P system contains a new library with reading and writing routines for OTF2. Basically, OTF2 is a full merge of its two predecessors that retains all their features, and it is planned to become the default data source for future versions of both Vampir and Scalasca. In this way, the user is free to choose between these two complementary tools to investigate the trace files and may select the one that is more appropriate for the specific question at hand. As an alternative to writing the trace data to disk and evaluating them post mortem, it is also possible to directly hand over the data to on-line analysis tools like Periscope. The corresponding interface that allows this on-line access is also an integral part of Score-P.

In profiling mode, the performance events are summarized at runtime separately for each call-path like in Scalasca. Additionally, support for phases, dynamic regions and parameter-based profiling has been integrated. The collected data is passed to the Score-P's profiling back-end CUBE4 for post mortem analysis using Scalasca or TAU or is used directly through the on-line access interface by Periscope. Also in profiling mode, Score-P supports the automatic detection of MPI wait states. Usually such inefficiencies are important bottlenecks and are thoroughly investigated by means of automatic trace analysis and subsequent visual analysis using a time-line representation. In the case of Score-P wait time profiling, inefficiencies are detected immediately when the respective MPI call is completed and stored as an additional metric in the call-path profile. In comparison to earlier versions of CUBE, this new one features a more powerful data model, more flexibility in the specification of system resource hierarchies and display parameters, and various techniques to enhance the efficiency that result in a much better scaling behavior of the analysis tool even in a range of tens of thousands of processes.

As a rough guideline for users who are uncertain which of these two modes to employ, we provide a brief comparison of their main advantages and disadvantages. Specifically, tracing mode allows to retain temporal and spatial connections, and it can reflect the dynamical behavior to an arbitrary precision. Moreover, statistical information and profiles may be derived from the program traces. On the other hand, the amount of data that is produced in the tracing mode can become prohibitively large; profiles tend to require much less storage space. In addition, the additional load that is imposed on the process, and hence the perturbations of the behavior of the code to be analyzed, are much smaller in profiling mode than in tracing mode. And finally we mention that the accurate synchronization of the clocks is an important aspect in tracing mode that may cause difficulties.

1.5 Acknowledgment

The development of Score-P was sponsored by a grant from the [German Federal Ministry of Education and Research](#) (Grant No. 01IH08006) within the framework of its High Performance Computing programme and with a grant from the [US Department of Energy](#) (Award No. DE-SC0001621). This support is gratefully acknowledged.

Chapter 2

Getting Started

In order to quickly introduce the user to the Score-P system, we explain how to build and install the tool and look at a simple example. We go through the example in full detail.

As mentioned above, the three core steps of a typical work cycle in the investigation of the behavior of a software package can be described as follows:

- *Instrumentation of user code*: Calls to the measurement system are inserted into the application. This can be done either fully automatically or with a certain amount of control handed to the software developer.
- *Measurement and analysis*: The instrumented application is executed under the control of the measurement system and the information gathered during the run time of this process is stored and analyzed.
- *Examination of results*: The information about the behavior of the code at run time is visualized and the user gets the opportunity to examine the reported results.

After building and installing the tool, we shall go through these three steps one after the other in the next sections. This will be followed by a full workflow example. For getting detailed presentations of available features, see [Section 3](#) for the instrumentation step and [Section 4](#) for the measurement.

2.1 Score-P Quick Installation

The Score-P performance analysis tool uses the GNU Autotools (Autoconf, Automake, Libtool and M4) build system. The use of Autotools allows Score-P to be build in many different systems with varying combinations of compilers, libraries and MPI implementations.

Autotools based projects are build as follows:

1. The available compilers and tools available are detected from the environment by the configure script.
2. Makefiles are generated based on the detected compilers and tools.
3. The generated Makefile project is then built and installed.

Score-P will have features enabled or disabled, based on the detection made by the Autotools generated configure script. The following 2 sub-sections cover mandatory prerequisites as well as optional features that are enabled based on what is available in the configured platform.

2.1.1 Prerequisites

To build Score-P, C, C++ and Fortran compilers and related tools are required. These can be available as modules (typically on super-computer environments) or as packages (on most Linux or BSD distributions).

For Debian based Linux systems using the APT package manager, the following command (as root) is sufficient to build Score-P with minimal features enabled:

```
apt-get install gcc g++ gfortran mpich2
```

On Red-Hat and derivative Linux systems running the YUM package manager, in a similar way:

```
yum install gcc g++ gfortran mpich2
```

For users of the SuperMUC, it is recommended to load the following modules:

```
module load ccomp/intel/12.1 fortran/intel/12.1 \  
mpi.ibm/5.2_PMR-fixes papi/4.9
```

2.1.2 General Autotools Build Options

System administrators can build Score-P with the familiar:

```
./configure && make && make install
```

The previous sequence of commands will detect compilers, libraries and headers, and then build and install Score-P in the following system directories:

2.1 Score-P Quick Installation

```
/usr/local/bin
/usr/local/lib
/usr/local/include
/usr/local/share
```

Users that are not administrators on the target machine may need to install the tool in an different location (due to permissions). The prefix flag should be specified with the target directory:

```
./configure --prefix=<installation directory>
```

For example, in the `install/scorep` directory on his/her home folder:

```
./configure --prefix=$HOME/install/scorep
```

In this case, the user's `PATH` variable needs to be updated to include the `bin` directory of Score-P, and the appropriate library and include folders specified (with `-L` and `-I`) when instrumenting and building applications.

Users of the SuperMUC (after loading the required modules mentioned previously), can issue the following command to configure Score-P:

```
./configure --prefix=$HOME/install/scorep --enable-static      \
--disable-shared --with-nocross-compiler-suite=intel          \
--with-mpi=openmpi --with-papi-header=$PAPI_BASE/include      \
--with-papi-lib=$PAPI_BASE/lib
```

2.1.3 Score-P Specific Build Options

In addition to general options available in all Autotools based build systems, there are Score-P configuration flags. These can be printed out by passing the `--help` flag to the configure script.

They are usually self explanatory. Here is a list of them with a short explanation:

- `--with-nocross-compiler-suite=` (gcc|ibm|intel|
pathscale|pgi|studio)

Specifies the compiler suite to use when not cross-compiling. Selecting one of the options sets all relevant variables to their expected names. These are CC, FC, F77, as well as the linker, preprocessor, etc.

- `--with-frontend-compiler-suite=` (gcc|ibm|intel|
pathscale|pgi|studio)

Similar to the previous configuration flag, but for cross-compiling environments.

- `--with-mpi=(mpich2|impi|openmpi)` The MPI compiler and runtime suite to use. Currently there are entries for MPICH2, Intel MPI and Open MPI.
- `--with-shmem=(openshmem|openmpi|sgimpt)` The SHMEM compiler suite to build this package in non cross-compiling mode. Usually autodetected. Needs to be in \$PATH.
- `--with-otf2=(yes|<otf2-bindir>)` An already install OTF2 can be specified with this flag. This is usually not necessary since OTF2 is built together with Score-P. Specify yes if the tool is in your \$PATH, otherwise specify the full path.
- `--with-opari2=(yes|<opari2-bindir>)` Similar to the previous configuration flag, but for OPARI2.
- `--with-cube=(yes|<cube-bindir>)` Similar to the previous two configuration flags, but for CUBE.

2.2 Instrumentation

Various analysis tools are supported by the Score-P infrastructure. Most of these tools are focused on certain special aspects that are significant in the code optimization process, but none of them provides the full picture. In the traditional workflow, each tool used to have its own measurement system, and hence its own instrumenter, so the user was forced to instrument his code more than once if more than one class of features of the application was to be investigated. One of the key advantages of Score-P is that it provides an instrumentation system that can be used for all the performance measurement and analysis tools, so that the instrumentation work only needs to be done once.

Internally, the instrumentation itself will insert special measurement calls into the application code at specific important points (events). This can be done in an almost automatic way using corresponding features of typical compilers, but also semi-automatically or in a fully manual way, thus giving the user complete control of the process. In general, an automatic instrumentation is most convenient for the user. However, this approach may lead to too many and/or too disruptive measurements, and for such cases it is then advisable to use selective manual instrumentation and measurement instead. For the moment, we shall however start the procedure in an automatic way to keep things simple for novice users.

To this end, we need to ask the Score-P instrumenter to take care of all the necessary instrumentation of user and MPI functions. This is done by using the `scorep` command that needs to be prefixed to all the compile and link commands usually employed to build the application. Thus, an application executable `app` that is

2.2 Instrumentation

normally generated from the two source files `app1.f90` and `app2.f90` via the command:

```
mpif90 app1.f90 app2.f90 -o app
```

will now be built by:

```
scorep mpif90 app1.f90 app2.f90 -o app
```

using the Score-P instrumenter.

In practice one will usually perform compilation and linking in separate steps, and it is not necessary to compile all source files at the same time (e.g., if makefiles are used). It is possible to use the Score-P instrumenter in such a case too, and this actually gives more flexibility to the user. Specifically, it is often sufficient to use the instrumenter not in all compilations but only in those that deal with source files containing MPI code. However, when invoking the linker, the instrumenter must *always* be used.

When makefiles are employed to build the application, it is convenient to define a placeholder variable to indicate whether a “preparation” step like an instrumentation is desired or only the pure compilation and linking. For example, if this variable is called `PREP` then the lines defining the C compiler in the makefile can be changed from:

```
MPICC = mpicc
```

to

```
MPICC = $(PREP) mpicc
```

(and analogously for linkers and other compilers). One can then use the same makefile to either build an instrumented version with the

```
make PREP="scorep"
```

command or a fully optimized and not instrumented default build by simply using:

```
make
```

in the standard way, i.e. without specifying `PREP` on the command line. Of course it is also possible to define the same compiler twice in the makefile, once with and once without the `PREP` variable, as in:

```
MPICC          = $(PREP) mpicc
MPICC_NO_INSTR =          mpicc
```

and to assign the former to those source files that must be instrumented and the latter to those files that do not need this.

2.3 Measurement and Analysis

Once the code has been instrumented, the user can initiate a measurement run using this executable. To this end, it is sufficient to simply execute the target application in the usual way, i.e.:

```
mpiexec $MPIFLAGS app [app_args]
```

in the case of an MPI or hybrid code, or simply:

```
app [app_args]
```

for a serial or pure OpenMP program. Depending on the details of the local MPI installation, in the former case the `mpiexec` command may have to be substituted by an appropriate replacement.

When running the instrumented executable, the measurement system will create a directory called `scorep-YYYYMMDD_HHMM_XXXXXXXX` where its measurement data will be stored. Here `YYYYMMDD` and `HHMM` are the date (in year-month-day format) and time, respectively, when the measurement run was started, whereas `XXXXXXXX` is an additional identification number. Thus, repeated measurements, as required by the optimization work cycle, can easily be performed without the danger of accidentally overwriting results of earlier measurements. The environment variables `SCOREP_ENABLE_TRACING` and `SCOREP_ENABLE_PROFILING` control whether event trace data or profiles are stored in this directory. By setting either variable to `true`, the corresponding data will be written to the directory. The default values are `true` for `SCOREP_ENABLE_PROFILING` and `false` for `SCOREP_ENABLE_TRACING`.

2.4 Report Examination

After the completion of the execution of the instrumented code, the requested data (traces or profiles) is available in the indicated locations. Appropriate tools can then be used to visualize this information and to generate reports, and thus to identify weaknesses of the code that need to be modified in order to obtain programs with a better performance. A number of tools are already available for this purpose. This includes, in particular, the [CUBE4 performance report explorer](#)

2.5 Simple Example

for viewing and analyzing profile data, [Vampir](#) for the investigation of trace information, and the corresponding components of the [TAU](#) toolsuite.

Alternatively, the [Periscope](#) system may be used to analyze the behaviour of the code on-line during its run time, i.e. (in contrast to the approaches mentioned above) *before* the end of the program run.

2.5 Simple Example

As a specific example, we look at a short C code for the solution of a Poisson equation in a hybrid (MPI and OpenMP) environment. The corresponding source code comes as part of the Score-P distribution under the *scorep/test/jacobi/* folder. Various other versions are also available - not only hybrid but also for a pure MPI parallelization, a pure OpenMP approach, and in a non-parallel way; and, in each case, not only in C but also in C++ and Fortran.

As indicated above, the standard call sequence:

```
mpicc -std=c99 -g -O2 -fopenmp -c jacobi.c
mpicc -std=c99 -g -O2 -fopenmp -c main.c
mpicc -std=c99 -g -O2 -fopenmp -o jacobi jacobi.o main.o -lm
```

that would first compile the two C source files and then link everything to form the final executable needs to be modified by prepending *scorep* to each of the three commands, i.e. we now have to write:

```
scorep mpicc -std=c99 -g -O2 -fopenmp -c jacobi.c
scorep mpicc -std=c99 -g -O2 -fopenmp -c main.c
scorep mpicc -std=c99 -g -O2 -fopenmp -o jacobi jacobi.o \
    main.o -lm
```

This call sequence will create a number of auxiliary C source files containing the original source code and a number of commands introduced by the measurement system in order to enable the latter to create the required measurements when the code is actually run. These modified source files are then compiled and linked, thus producing the desired executable named *jacobi*.

The actual measurement process is then initiated, e.g., by the call:

```
mpiexec -n 2 ./jacobi
```

The output data of this process will be stored in a newly created experiment directory *scorep-YYYYMMDD_HHMM_XXXXXXXX* whose name is built up from the date and time when the measurement was started and an identification number.

As we had not explicitly set any Score-P related environment variables, the profiling mode was active by default. We obtain a file called *profile.cubex* containing profiling data in the experiment directory as the result of the measurement run. This file can be visually analyzed with the help of CUBE.

If we had set the variable `SCOREP_ENABLE_TRACING` to `true`, we would additionally have obtained trace data, namely the so called anchor file `traces.otf2` and the global definitions `traces.def` as well as a subdirectory `traces` that contains the actual trace data. This trace data is written in Open Trace Format 2 (OTF2) format. OTF2 is the joint successor of the classical formats OTF (used, e. g., by Vampir) and Epilog (used by Scalasca). A tool like Vampir can then be used to give a visual representation of the information contained in these files.

Chapter 3

Application Instrumentation

Score-P provides several possibilities to instrument user application code. Besides the automatic compiler-based instrumentation (Section 3.1), it provides manual instrumentation using the Score-P User API (Section 3.2), semi-automatic instrumentation using POMP2 directives (Section 3.6) and, if configured, automatic source-code instrumentation using the PDToolkit-based instrumenter (Section 3.8).

As well as user routines and specified source regions, Score-P currently supports the following kinds of events:

- **MPI library calls:**

Instrumentation is accomplished using the standard MPI profiling interface PMPI. To enable it, the application program has to be linked against the Score-P MPI (or hybrid) measurement library plus MPI-specific libraries. Note that the Score-P libraries must be linked *before* the MPI library to ensure interposition will be effective.

- **library calls:**

Instrumentation is accomplished using the profiling interface or the GNU linker for library wrapping. To enable it, the application program has to be linked against the Score-P (or hybrid) measurement library plus -specific libraries. Note that the Score-P libraries must be linked *before* the library to ensure interposition will be effective.

- **OpenMP directives & API calls:**

The Score-P measurement system uses the OPARI2 tool for instrumentation of OpenMP constructs. See the OPARI2 documentation on how to instrument OpenMP source code. In addition, the application must be linked with the Score-P OpenMP (or hybrid) measurement library.

- **Pthread library calls:**

The Score-P measurement system uses GNU linker for instrumentation of Pthreads library calls. At the moment only a few library calls are supported.

The Score-P instrumenter command `scorep` automatically takes care of compilation and linking to produce an instrumented executable, and should be prefixed to compile and link commands. Often this only requires prefixing definitions for `CC` or `MPICC` (and equivalents) in Makefiles.

Usually the Score-P instrumenter `scorep` is able to automatically detect the programming paradigm from the set of compile and link options given to the compiler. In some cases however, when the compiler or compiler wrapper enables specific programming paradigm by default (e.g., Pthreads on Cray and Blue Gene/Q systems), `scorep` needs to be made aware of the programming paradigm in order to do the correct instrumentation. Please see `scorep --help` for the available options.

When using Makefiles, it is often convenient to define a "preparation preposition" placeholder (e.g., `PREP`) which can be prefixed to (selected) compile and link commands:

```
MPICC  = $(PREP) mpicc
MPICXX = $(PREP) mpicxx
MPIF90 = $(PREP) mpif90
```

These can make it easier to prepare an instrumented version of the program with

```
make PREP="scorep"
```

while default builds (without specifying `PREP` on the command line) remain fully optimized and without instrumentation.

In order to instrument applications which employ GNU Autotools for building, following instrumentation procedure has to be used:

1. Configure application as usual, but provide additional argument:
`--disable-dependency-tracking`
2. Build application using `make` command with compiler specification variables set as follows:

```
make CC="scorep <your-cc-compiler>" \
CXX="scorep <your-cxx-compiler>" \
FC="scorep <your-fc-compiler>" ...
```

When compiling without the Score-P instrumenter, the `scorep-config` command can be used to simplify determining the appropriate linker flags and libraries, or include paths:

```
scorep-config [--mpp=none|--mpp=mpi|--mpp=shmem] \
[--thread=none|--thread=omp|--thread=pthread] --libs
```

The `--mpp=<paradigm>` switch selects which message passing paradigm is used. Currently, Score-P supports applications using MPI (`--mpp=mpi`) or SHMEM (`--mpp=shmem`) and applications without any message passing paradigm. It is not possible to specify two message passing systems for the same application. The `--thread=<paradigm>` switch selects which threading system is used in Score-P. You may use OpenMP (`--thread=omp`), no threading system (`--thread=none`) or POSIX threading system (`--thread=pthread`). It is not possible to specify two threading systems for the same application. However, you may combine a message passing system with a threading system.

Note

A particular installation of Score-P may not offer all measurement configurations!

The `scorep-config` command can also be used to determine the right compiler flags for specifying the include directory of the `scorep/SCOREP_User.h` or `scorep/SCOREP_User.inc` header files. When compiling without using the Score-P instrumenter, necessary defines and compiler instrumentation flags can be obtained by calling one of the following, depending on the language:

```
scorep-config --cflags [<options>]
scorep-config --cxxflags [<options>]
scorep-config --fflags [<options>]
```

If you compile a C file, you should use `--cflags`. If you use a C++ program, you should use `--cxxflags`. And if you compile a Fortran source file, you should use `--fflags`.

With the additional options it is possible to select the used adapter, the threading system and the message passing system. For each adapter, we provides a pair of flags of the form `--adapter`, and `--noadapter` (please replace `adapter` by the name of the adapter). This allows to get options for non-default instrumentation possibilities. E.g., `--user` enables the manual instrumentation with the Score-P user API, the `--nocompiler` option disables compiler instrumentation.

Score-P supports a variety of instrumentation types for user-level source routines and arbitrary regions, in addition to fully-automatic MPI and OpenMP instrumentation, as summarized in Table 3.1.

When the instrumenter determines that MPI or OpenMP are being used, it automatically enables MPI library instrumentation or OPARI2-based OpenMP instrumentation, respectively. The default set of instrumented MPI library functions is specified when Score-P is installed. All OpenMP parallel constructs and API calls are instrumented by default.

Table 3.1: Score-P instrumenter option overview

Type of instrumentation	Instrumenter switch	Default value	Instrumented routines	Runtime measurement control
MPI	--mpp=mpi/ --mpp=none	(auto)	configured by install	see Sec. 4.5.1
SHMEM	--mpp=shmem/ --mpp=none	(auto)	configured by install	–
OpenMP	--thread=omp/ --thread=none	(auto)	all parallel constructs	–
Pthread	--thread=pthread	(auto)	Basic Pthread library calls	–
Compiler, Sec. 3.1	--compiler/ --nocompiler	enabled	all	Filtering, Sec. 4.3
PDT, Sec. 3.8	--pdt/ --nopdt	disabled	all	Filtering, Sec. 4.3
POMP2 user regions, Sec. 3.6	--pomp/ --nopomp	depends on OpenMP usage	manually annotated	Filtering, Sec. 4.3
Manual, Sec. 3.2	--user/ --nouser	disabled	manually annotated	Filtering, Sec. 4.3 , and selective recording, Sec. 4.4

By default, automatic instrumentation of user-level source routines by the compiler is enabled (equivalent to specifying `--compiler`). The compiler instrumentation can be disabled with `--nocompiler` when desired, such as when using PDToolkit, or POMP2 or Score-P user API manual source annotations, are enabled with `--pdt`, `--pomp` and `--user`, respectively. Compiler, PDToolkit, POMP2 and Score-P user API instrumentation can all be used simultaneously, or in arbitrary combinations, however, it is generally desirable to avoid instrumentation duplication (which would result if all are used to instrument the same routines). Note that enabling PDToolkit instrumentation automatically enables Score-P user instrumentation, because it inserts Score-P user macros into the source code.

Note

There are two ways of internal data handling for measurements involving the OpenMP threading model. The possible options are:

`--thread=omp:pomp_tpd`

`--thread=omp:ancestry`

These options should be identical in behavior. If you specify `--thread=omp` or OpenMP is automatically detected, the default is `pomp_tpd`.

Sometimes it is desirable to explicitly direct the Score-P instrumenter to do nothing except execute the associated compile/link command. For such cases it is possible to disable default instrumentation with `--nocompiler`, `--thread=none`, and/or `--mpp=none`. Although no instrumentation is performed, this can help verify that the Score-P instrumenter correctly handles the compile/link commands.

Note

Disabling OpenMP in the instrumenter for OpenMP applications will cause errors during program execution if any event occurs inside of a parallel region.

Each thread model uses a default internal locking mechanism for the Score-P measurement system. For the standard use case there is no need to specify an explicit locking mode. However, on certain systems or for performance reasons it might be useful to change the locking mode. For these cases the instrumenter provides the option `--mutex=[omp|pthread|pthread:spinlock|pthread:wrap|none]`. Current possibilities are the OpenMP locking (`omp`), Pthread mutex (`pthread`), Pthread spinlock (`pthread:spinlock`), Pthread mutex, where original functions replaced with `__real` functions (`pthread:wrap`), and none at all (`none`). Which of these are available for a given installation will be determined at configure time.

Note

Not all combinations of thread model and explicit choice of locking are useful. Currently, only the combination of no locking with a real threading system is overwritten by the thread model default to ensure thread safety.

3.1 Automatic Compiler Instrumentation

Most current compilers support automatic insertion of instrumentation calls at routine entry and exit(s), and Score-P can use this capability to determine which routines are included in an instrumented measurement.

Compiler instrumentation of all routines in the specified source file(s) is enabled by default by Score-P, or can be explicitly requested with `--compiler`. Compiler instrumentation is disabled with `--nocompiler`.

Note

Depending on the compiler, and how it performs instrumentation, insertion of instrumentation may disable in-lining and other significant optimizations, or in-lined routines may not be instrumented at all (and therefore "invisible").

Automatic compiler-based instrumentation has been tested with a number of different compilers:

- GCC (UNIX-like operating systems, not tested with Windows)
- IBM xlc, xLC (version 7 or later, IBM Blue Gene)
- IBM xlf (version 9.1 or later, IBM Blue Gene)
- PGI (on Linux)
- Intel compilers (version 10 or later, Linux)
- SUN Studio compilers (Linux, Fortran only)

In all cases, Score-P supports automatic instrumentation of C, C++ and, Fortran codes, except for the SUN Studio compilers which only provide appropriate support in their Fortran compiler.

Note

The automatic compiler instrumentation might create a significant relative measurement overhead on short function calls. This can impact the overall application performance during measurement. C++ applications are especially prone to suffer from this, depending on application design and whether C++ STL functions are also instrumented by the compiler. Currently, it is not possible to prevent the instrumentation of specific functions on all platforms when using automatic compiler instrumentation.

Names provided for instrumented routines depend on the compiler, which may add underscores and other decorations to Fortran and C++ routine names, and whether name "demangling" has been enabled when Score-P was installed and could be applied successfully.

3.2 Manual Region Instrumentation

3.2 Manual Region Instrumentation

In addition to the automatic compiler-based instrumentation (see Section 3.1), instrumentation can be done manually. Manual instrumentation can also be used to augment automatic instrumentation with region or phase annotations, which can improve the structure of analysis reports. Furthermore, it offers the possibility to record additional, user defined metrics. Generally, the main program routine should be instrumented, so that the entire execution is measured and included in the analysis.

Instrumentation can be performed in the following ways, depending on the programming language used.

Fortran:

```
#include "scorep/SCOREP_User.inc"

subroutine foo
  SCOREP_USER_REGION_DEFINE( my_region_handle )
  ! more declarations

  SCOREP_USER_REGION_BEGIN( my_region_handle, "foo",
    SCOREP_USER_REGION_TYPE_COMMON )
  ! do something
  SCOREP_USER_REGION_END( my_region_handle )

end subroutine foo
```

C/C++:

```
#include <scorep/SCOREP_User.h>

void foo()
{
  SCOREP_USER_REGION_DEFINE( my_region_handle )

  // more declarations

  SCOREP_USER_REGION_BEGIN( my_region_handle, "foo",
    SCOREP_USER_REGION_TYPE_COMMON )

  // do something

  SCOREP_USER_REGION_END( my_region_handle )
}
```

C++ only:

```
#include <scorep/SCOREP_User.h>

void foo()
```

CHAPTER 3. APPLICATION INSTRUMENTATION

```
{
    SCOREP_USER_REGION( "foo", SCOREP_USER_REGION_TYPE_FUNCTION )

    // do something
}
```

Note

When using Fortran, make sure the C preprocessor expands the macros. In most cases, the fortran compiler invoke the C preprocessor if the source file suffix is in capital letters. However, some compilers provide extra flags to tell the compiler to use a C preprocessor. Furthermore, it is important to use the C-like `#include` with the leading `'#'`-character to include the `SCOREP_User.inc` header file. Otherwise, the inclusion may happen after the C preprocessor ran. As result the fortran compiler complains about unknown preprocessing directives.

Region handles (`my_region_handle`) should be registered in each annotated function/subroutine prologue before use within the associated body, and should not already be declared in the same program scope.

For every region, the region type can be indicated via the region type flag. Possible region types are:

SCOREP_USER_REGION_TYPE_COMMON Indicates regions without a special region type.

SCOREP_USER_REGION_TYPE_FUNCTION Indicates that the region is a function or subroutine

SCOREP_USER_REGION_TYPE_LOOP Indicates that the region is the body of a loop, with the same number of iterations in all locations.

SCOREP_USER_REGION_TYPE_DYNAMIC Set this type to create a separate branch in the call-tree for every execution of the region. See Section [4.1.3](#).

SCOREP_USER_REGION_TYPE_PHASE Indicates that this region belongs to a special phase. See Section [4.1.2](#).

To create a region of combined region types you can connect two or more types with the binary OR-operator, e.g.:

```
SCOREP_USER_REGION_BEGIN( handle, "foo",
    SCOREP_USER_REGION_TYPE_LOOP |
    SCOREP_USER_REGION_TYPE_PHASE |
    SCOREP_USER_REGION_TYPE_DYNAMIC )
```

3.2 Manual Region Instrumentation

For function instrumentation in C and C++, Score-P provides macros, which automatically pass the name and function type to Score-P measurement system. The `SCOREP_USER_FUNC_BEGIN` macro contains a variable definition. Thus, compilers that require strict separation of declaration and execution part, may not work with this macro.

C/C++:

```
#include <scorep/SCOREP_User.h>

void foo()
{
    SCOREP_USER_FUNC_BEGIN()
    // do something
    SCOREP_USER_FUNC_END()
}
```

In some cases, it might be useful to have the possibility to define region handles with a global scope. In C/C++, a region handle can be defined at a global scope with `SCOREP_USER_GLOBAL_REGION_DEFINE`. In this case, the `SCOREP_USER_REGION_DEFINE` must be omitted. The `SCOREP_USER_GLOBAL_REGION_DEFINE` must only appear in one file. To use the same global variable in other files, too, declare the global region in other files with `SCOREP_USER_GLOBAL_REGION_EXTERNAL`.

File 1:

```
SCOREP_USER_GLOBAL_REGION_DEFINE( global_handle )

foo()
{
    SCOREP_USER_REGION_BEGIN( global_handle, "phase 1",
                             SCOREP_USER_REGION_TYPE_PHASE)
    // do something
    SCOREP_USER_REGION_END( global_handle )
}
```

File 2:

```
SCOREP_USER_GLOBAL_REGION_EXTERNAL( global_handle )

bar()
{
    SCOREP_USER_REGION_BEGIN( global_handle, "phase 1",
                             SCOREP_USER_REGION_TYPE_PHASE)
    // do something
    SCOREP_USER_REGION_END( global_handle )
}
```

Note

These macros are not available in Fortran.

The source files instrumented with Score-P user macros have to be compiled with `-DScoreP_USER_ENABLE` otherwise `ScoreP_*` calls expand to nothing and are ignored. If the Score-P instrumenter `--user` flag is used, the `ScoreP_USER_ENABLE` symbol will be defined automatically. Also note, that Fortran source files instrumented this way have to be preprocessed with the C preprocessor (CPP).

Manual routine instrumentation in combination with automatic source-code instrumentation by the compiler or PDT leads to double instrumentation of user routines, i.e., usually only user region instrumentation is desired in this case.

3.3 Instrumentation for Parameter-Based Profiling

The Score-P user API provides also macros for parameter-based profiling. In parameter-based profiling, the parameters of a function are used to split up the call-path for executions of different parameter values. In Score-P parameter-based profiling is supported for integer and string parameters. To associate a parameter value to a region entry, insert a call to `ScoreP_USER_PARAMETER_INT64` for signed integer parameters, `ScoreP_USER_PARAMETER_UINT64` for unsigned integer parameters, or `ScoreP_USER_PARAMETER_STRING` for string parameters after the region entry (e.g. after `ScoreP_USER_REGION_BEGIN` or `ScoreP_USER_FUNC_BEGIN`).

Fortran:

```
#include "scorep/ScoreP_User.inc"

subroutine foo(i, s)
  integer :: i
  character (*) :: s

  ScoreP_USER_REGION_DEFINE( my_region_handle )
  ScoreP_USER_PARAMETER_DEFINE( int_param )
  ScoreP_USER_PARAMETER_DEFINE( string_param )
  ScoreP_USER_REGION_BEGIN( my_region_handle, "my_region",
ScoreP_USER_REGION_TYPE_COMMON )
  ScoreP_USER_PARAMETER_INT64(int_param, "myint",i)
  ScoreP_USER_PARAMETER_UINT64(uint_param, "myuint",i)
  ScoreP_USER_PARAMETER_STRING(string_param, "mystring",s)

  // do something

  ScoreP_USER_REGION_END( my_region_handle )
end subroutine foo
```

C/C++:

```
#include <scorep/ScoreP_User.h>
```


3.4 Measurement Control Instrumentation

```
void foo(int64_t myint, uint64_t myuint, char *mystring)
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    SCOREP_USER_REGION_BEGIN( my_region_handle, "foo",
    SCOREP_USER_REGION_TYPE_COMMON )
    SCOREP_USER_PARAMETER_INT64("myint",myint)
    SCOREP_USER_PARAMETER_UINT64("myuint",myuint)
    SCOREP_USER_PARAMETER_STRING("mystring",mystring)

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

In C/C++, only a name for the parameter and the value needs to be provided. In Fortran, the handle must be defined first with `SCOREP_USER_PARAMETER_DEFINE`. The defined handle name must be unique in the current scope. The macro `SCOREP_USER_PARAMETER_INT64` as well as the macro `SCOREP_USER_PARAMETER_STRING` need the handle as the first argument, followed by the name and the value.

3.4 Measurement Control Instrumentation

The Score-P user API also provides several macros for measurement control that can be incorporated in source files and activated during instrumentation. The macro `SCOREP_RECORDING_OFF` can be used to (temporarily) pause recording until a subsequent `SCOREP_RECORDING_ON`. Just like the already covered user-defined annotated regions, `SCOREP_RECORDING_ON` and the corresponding `SCOREP_RECORDING_OFF` must be correctly nested with other enter/exit events. Finally, with `SCOREP_RECORDING_IS_ON` you can test whether recording is switched on.

Events are not recorded when recording is switched off (though associated definitions are), resulting in smaller measurement overhead. In particular, traces can be much smaller and can target specific application phases (e.g., excluding initialization and/or finalization) or specific iterations. Since the recording switch is process-local, and effects all threads on the process, it can only be initiated outside of OpenMP parallel regions. Switching recording on/off is done independently on each MPI process without synchronization.

Note

Switching recording on/off may result in inconsistent traces or profiles, if not applied with care. In particular, if communication is recorded incomplete (e.g. if the send is missing but the corresponding receive event is recorded) it may

result in errors during execution or analysis. Furthermore, it is not possible to switch recording on/off from within parallel OpenMP regions. We recommend to use the selective recording interface, instead of the manual on/off switch whenever possible. Special care is required in combination with selective recording (see Section 4.4, which also switches recording on/off).

3.5 Source-Code Instrumentation Enabling Online Access

The Online Access interface to the measurement system of Score-P allows remote control of measurement and access to the profile data. The online access interface may not be available on all platforms. To use the Online Access interface, Score-P must have been built with Online Access (OA) support.

The Online Access module requires the user to specify at least one *online access phase*. The online access phase does not show the behavior of a region of type phase as defined in Section 3.2. However, the way to specify an online access phase is similar to manual region instrumentation. The start and end of the online access phase defines the interaction points, where new measurement control commands are applied and data requests are answered.

To insert an online online access phase into the code, the user has to insert the macros `SCOREP_USER_OA_PHASE_BEGIN` and the corresponding `SCOREP_USER_OA_PHASE_END` at appropriate locations. These macros must be

- correctly nested with all regions and
- must be potential global synchronization points.

Common practice is to mark the body of the application's main loop as online access phase, in order to utilize the main loop iterations for iterative online analysis. Only the measurements collected inside the OA phase could be configured and retrieved.

Instrumentation can be performed in the following ways, depending on the programming language used.

Fortran:

```
#include "scorep/SCOREP_User.inc"

subroutine foo
  SCOREP_USER_REGION_DEFINE( my_region_handle )
  ! more declarations

  SCOREP_USER_OA_PHASE_BEGIN( my_region_handle, "foo",
    SCOREP_USER_REGION_TYPE_COMMON )
  ! do something
```

3.6 Semi-Automatic Instrumentation of POMP2 User Regions

```
SCOREP_USER_OA_PHASE_END( my_region_handle )

end subroutine foo
```

C/C++:

```
#include <scorep/SCOREP_User.h>

void foo()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // do something

    SCOREP_USER_OA_PHASE_BEGIN( my_region_handle, "foo",
    SCOREP_USER_REGION_TYPE_COMMON )

    // do something

    SCOREP_USER_OA_PHASE_END( my_region_handle )
}
```

3.6 Semi-Automatic Instrumentation of POMP2 User Regions

If you manually instrument the desired user functions and regions of your application source files using the POMP2 `INST` directives described below, the Score-P instrumenter `--pomp` flag will generate instrumentation for them. It is automatically enabled for OpenMP applications, but can be disabled with `--nopomp`. POMP2 instrumentation directives are supported for Fortran and C/C++. The main advantages are that

- being directives, the instrumentation is ignored during "normal" compilation and
- this semi-automatic instrumentation procedure can be used when fully automatic compiler instrumentation is not supported.

The `INST BEGIN/END` directives can be used to mark any user-defined sequence of statements. If this block has several exit points (as is often the case for functions), all but the last have to be instrumented by `INST ALTEND`.

Fortran:

```
subroutine foo(...)
!declarations
!POMP$ INST BEGIN(foo)
...
if (<condition>) then
```

CHAPTER 3. APPLICATION INSTRUMENTATION

```
        !POMP$ INST ALTEND(foo)
        return
    end if
    ...
    !POMP$ INST END(foo)
end subroutine foo
```

C/C++:

```
void foo(...)
{
    /* declarations */
    #pragma pomp inst begin(foo)
    ...
    if (<condition>)
    {
        #pragma pomp inst altend(foo)
        return;
    }
    ...
    #pragma pomp inst end(foo)
}
```

At least the main program function has to be instrumented in this way, and additionally, one of the following should be inserted as the first executable statement of the main program:

Fortran:

```
program main
    ! declarations
    !POMP$ INST INIT
    ...
end program main
```

C/C++:

```
int main(int argc, char** argv)
{
    /* declarations */
    #pragma pomp inst init
    ...
}
```

Note

The POMP2 instrumentation uses the OPARI2 instrumenter. Thus, for OpenMP application, which automatically enable OPARI2 to instrument the parallel constructs, POMP2 user region instrumentation is enabled, too. To disable POMP2 user region instrumentation for OpenMP applications, pass `--nopomp` to the instrumenter.

3.7 Preprocessing before POMP2 and OpenMP instrumentation

By default, the source code is preprocessed before POMP2 instrumentation happens. For more information on the preprocessing, see Section [3.7](#).

3.7 Preprocessing before POMP2 and OpenMP instrumentation

By default, source files are preprocessed before the semi-automatic POMP2 instrumentation or the OpenMP construct instrumentation with OPARI2 happens. This ensures, that all constructs and regions that might be contained in header files, templates, or macros are properly instrumented. Furthermore, conditional compilation directives take effect, too. The necessary steps are performed by the Score-P instrumenter tool.

Some Fortran compilers do not regard information about the original source location that the preprocessing leaves in the preprocessed code. This causes wrong source code information for regions from compiler instrumentation, and manual source code instrumentation. However, these compilers also disregard the source code information left by OPARI2. Thus, for these compilers the source location information is incorrect anyway.

If the preprocessing is not desired, you can disable it with the `--nopreprocess` flag. In this case the instrumentation is performed before the preprocessing happens. In this case constructs and regions in header files, macros, or templates are not instrumented. Conditional compilation directives around constructs may also lead to broken instrumentation.

Note

If a parallel region is not instrumented, the application will crash during runtime.

The preprocessing does not work in combination with PDT source code instrumentation. Thus, if PDT instrumentation is enabled, it changes the default to not preprocess a source file. If you manually specify preprocessing and PDT source code instrumentation, the instrumenter will abort with an error.

3.8 Source-Code Instrumentation Using PDT

If Score-P has been configured with PDToolkit support, automatic source-code instrumentation can be used as an alternative instrumentation method. In this case, the source code of the target application is pre-processed before compilation, and appropriate Score-P user API calls will be inserted automatically. However, please note that this feature is still somewhat experimental and has a number of limitations (see Section [3.8.1](#)).

CHAPTER 3. APPLICATION INSTRUMENTATION

To enable PDT-based source-code instrumentation, call `scorep` with the `--pdt` option, e.g.,

```
scorep --pdt mpicc -c foo.c
```

This will by default instrument all routines found in `foo.c`. (To avoid double instrumentation, automatic compiler instrumentation is disabled when using Source-Code Instrumentation with PDT. However, if you you can enforce additional compiler instrumentation with `--compiler`.)

3.8.1 Limitations

Currently the support for the PDT-based source-code instrumenter still has a number of limitations:

- When instrumenting Fortran 77 applications, the inserted instrumentation code snippets do not yet adhere to the Fortran 77 line length limit. Typically, it is possible to work around this issue by supplying extra command line flags (e.g., `-ffixed-line-length-132` or `-qfixed=132`) to the compiler.
- Code in C/C++ header files as well as included code in Fortran (either using the C preprocessor or the `include` keyword) will currently not be instrumented.
- Support for C++ templates and classes is currently only partially implemented.
- Advanced TAU instrumentation features such as static/dynamic timers, loop, I/O and memory instrumentation are not yet supported. Respective entries in the selective instrumentation file will be ignored.

3.9 Binary Instrumentation Using Cobi

If you have an installation of the binary instrumenter Cobi, you can configure Score-P to support binary instrumentation of functions with Cobi during Score-P installation. To use Cobi for function instrumentation, you must set the `--cobi` flag. E.g.

```
scorep --cobi mpicc foo.c -o foo
```

By default, it will disable automatic compiler instrumentation during compilation and instrument all function in the executable. Although the instrumentation happens after linking, we recommend to compile all objects with the `--cobi` flag to

3.10 Enforce Linking of Static/Shared Score-P Libraries

avoid double instrumentation. However, you can enforce compiler instrumentation with `--compiler`.

Note

Cobi is still considered to be an experimental tool. Thus, it may have some limitations. E.g. it is currently only available for GNU compilers and requires Score-P to be build in shared mode. Also the support for Cobi itself is limited.

3.10 Enforce Linking of Static/Shared Score-P Libraries

If the Score-P was build with shared libraries and with static libraries, the instrumenter uses the compiler defaults for linking. E.g. if the compiler chooses shared libraries by default, the instrumenter will link your application with the shared Score-P libraries. Furthermore, the linking is affected by parameters in the original link command. E.g. if your link command contains a `-Bstatic` flag, afterwards appended Score-P libraries are also linked statically.

If you want to override the default and enforce linking of static or dynamic Score-P libraries, you can add the flag `--static` or `--dynamic` for the instrumenter. E.g. a command to enforce static linking can look like:

```
scorep --static mpicc foo.c -o foo
```

In this case, the linking against the static version of the Score-P libraries is enforced.

If enforcing static or dynamic linking is not possible on your system, e.g., because no static/dynamic Score-P libraries are installed, the instrumenter will abort with an error. You can determine whether `--static` or `--dynamic` is available from the output of `scorep --help`. If the `--static` or `--dynamic` flags are not shown, then they are not available.

Chapter 4

Application Measurement

If an application was instrumented with Score-P, you will get an executable, which you can execute like the uninstrumented application. After the application run, you will find an experiment directory in your current working directory, which contains all recorded data. The experiment directory has the format `scorep-YYYYMMDD_HHMM_XXXXXXXX`, where `YYYYMMDD` and `HHMM` encodes the date followed by a series of random numbers. You may specify the name of the experiment directory by setting the environment variable `SCOREP_EXPERIMENT_DIRECTORY` to the desired name of the directory. If the directory already exists, the existing directory will be renamed by appending a date like above by default. You can let Score-P abort the measurement immediately by setting `SCOREP_OVERWRITE_EXPERIMENT_DIRECTORY` to `false` if the experiment directory already exists. This has only an effect if `SCOREP_EXPERIMENT_DIRECTORY` was set too.

In general, you can record a profile and/or a event trace. Whether a profile and/or a trace is recorded, is specified by the environment variables `SCOREP_ENABLE_PROFILING` and `SCOREP_ENABLE_TRACING`. If the value of this variables is zero or `false`, profiling/tracing is disabled. Otherwise Score-P will record a profile and/or trace. By default, profiling and tracing are both enabled.

You may start with a profiling run, because of its lower space requirements. According to profiling results, you may configure the trace buffer limits, filtering or selective recording for recording traces.

Score-P allows to configure several parameters via environment variables. After the measurement run you can find a `scorep.cfg` file in your experiment directory which contains the configuration of the measurement run. If you had not set configuration values explicitly, the file will contain the default values. This file is safe to be used as input for a POSIX shell. For example if you want to reuse the same configuration from an previous measurement run something like this:

```
$ set -a
```

```
$ . scorep.cfg  
$ set +a
```

4.1 Profiling

Score-P implements a call-tree based profiling system. Every node in the call tree represent a recorded region. The edges of the tree represent the caller-callee relationship: The children of a node are those regions, that are entered/exited within a region. The path from the root to an arbitrary node, represents a call-path. Thus, every node in the tree identifies also the call-path from the root to itself.

Together with a node, the statistics for the call-path are stored. By default, the runtime and the number of visits are recorded. Additionally, hardware counters can be configured and are stored for every call-path. User defined metrics are only stored in those nodes, where the metric was triggered.

For enabling profiling, set the `SCOREP_ENABLE_PROFILING` environment variable to 1 or `true`. After the execution of your application you will then find a file, named `profile.cubex` in your measurement directory, which you can display with the CUBE4 with `cube-qt profile.cubex`. The name of the profile can be changed through the environment variable `SCOREP_PROFILING_BASE_NAME`. The extension `.cubex` will be appended to the base name you specify in the environment variable `SCOREP_PROFILING_BASE_NAME`.

By default, Score-P writes the profile in CUBE4 base format. Hereby, for every metric contains one value, usually only the sum. However, Score-P allows to store the profile in two other formats. To change the default format, set the environment variable `SCOREP_PROFILING_FORMAT`. The following formats are available:

- **CUBE4** is the default format.
- **CUBE_TUPLE** is an extended CUBE format. It provides a tuple of sum, minimum, maximum, number of samples, sum of squares for every metric.
- **TAU_SNAPSHOT** is a textual format used by TAU. It creates a file per location and thus, may not scale to large machines.

Score-P records a call tree profile. The maximum call-path depth that is recorded is limited to 30, by default. This avoids extremely large profiles for recursive calls. However, this limit can be changed with the environment variable `SCOREP_PROFILING_MAX_CALLPATH_DEPTH`.

4.1 Profiling

4.1.1 Parameter-Based Profiling

Parameter-based profiling allows to separate the recoded statistics for a region, depending on the values of one or multiple parameters. In the resulting call-tree, each occurred parameter-value will create a sub-node of the region. Every parameter has a parameter name. Thus, if multiple parameters are used, they can be distinguished and split the call-tree in the order of the parameter events. In the final call-tree it looks like every parameter-name/parameter-value pair is a separate region.

Currently, the only source for parameter events is manual instrumentation (see Section 3.3).

4.1.2 Phase Profiling

Phase-profiling allows, to group the execution of the application into logical phases. Score-P records a separate call-tree for every phase in the application. A phase starts when a region of type `SCOREP_USER_REGION_TYPE_PHASE` (see Section 3.2) is entered. If the region is exited, the phase is left. If two phases are nested, then the outer phase is left, when the inner phase is entered. If the inner phase is exited, the outer phase is re-entered. Figure 4.1 shows the difference in the call-tree if the regions with the names `phase1` and `phase2` are not of type `SCOREP_USER_REGION_TYPE_PHASE` on the left side and the forest if they are of type `SCOREP_USER_REGION_TYPE_PHASE` on the right side.

If the phase consists of multiple partitions, and thus cannot be enclosed by a single code region, all code-regions that form the phase must have the same region handle. The possibility to define global region handles in C/C++ might be useful for the definition of phases that are have multiple partitions (see Section 3.2).

4.1.3 Dynamic Region Profiling

When profiling, multiple visits of a call-path are summarized. However, e.g, for investigations in time-dependent behavior of an application, each iteration of a main loop (or some other region) should create a separate profile sub-tree. For such cases, Score-P allows to define regions to be of type `dynamic`. For dynamic regions, each entry of the region will create a separate path. For this cause, the Score-P profiling system creates an extra parameter, named `instance`. On each visit to a dynamic region, the `instance` parameter for this call-path is increased and triggered automatically. Thus, the every visit to a dynamic region generates a separate subtree in the profile.

As an example, let us assume that an application contains the regions `foo` and `main`, where `main` calls `foo` three times. A regular profile would show two call-paths:




Figure 4.1: Call-tree changes when using phases. The left side shows the calltree if no region is of type phase. The right side shows the call-tree forest with phases.

- main
- main/foo

If `foo` is a dynamic region, the profile would contain additional sub-nodes for each visit of `foo`. The resulting profile would contain the following call-paths:

- main
- main/foo
- main/foo/instance=0
- main/foo/instance=1
- main/foo/instance=2

In this case `main/foo` contains the summarized statistics for all 3 visits, while `main/foo/instance=0` contains the statistics for the first visits of the call-path.

4.1 Profiling

Note

The enumeration of the instance is per call-path and not per dynamic region. In particular, if a dynamic region `foo` appears in 2 call-paths, it has 2 instance number 0, one in both call-paths. It is not a global enumeration of the visits to `foo` but enumerates the visits of `foo` in a particular call-path from 0 to N.

Currently, the only possibility to define dynamic regions is via the manual region instrumentation, described in Section 3.2.

Note

Using dynamic regions can easily create very large profiles. Thus, use this feature with care. If you are only interested in some parts of the application, selective recording (see Section 4.4) might be a memory space save alternative. Furthermore, you can use clustering (see Section 4.1.4) to reduce the memory requirements.

4.1.4 Clustering

Clustering allows to reduce the memory requirements of a dynamic region, by clustering similar sub-trees into one cluster. A visualization tool (like CUBE 4) might expand the clusters back to single iterations transparently. You can enable/disable clustering via the environment variable `SCOREP_PROFILING_ENABLE_CLUSTERING`. By default, clustering is enabled.

Currently, clustering is limited to the instances of one node in the call-tree. If a dynamic region appears on several call-paths, Score-P will only cluster one, and generate separate sub-trees for every iterations in all other call-paths. By default, Score-P will cluster the instances of that dynamic region call-path that it enters first. If you have only one call-path where a dynamic region occurs (e.g., if the body of the main loop is the only dynamic region), this region will be clustered automatically. Otherwise, we recommend to specify the region you want to cluster in the environment variable `SCOREP_PROFILING_CLUSTERED_REGION`.

Note

If the selected region appears on multiple call-paths, only one of them is clustered. Score-P chooses the call-path of that regions that it enters first. In particular, if the selected dynamic region is nested into itself, the outermost occurrence is clustered.

Furthermore, the clustered region must not be inside of a parallel region, but must be at a sequential part of the program. However, the clustered region may contain parallel regions.

Table 4.1: Clustering modes

Mode	Description
0	No structural similarity required.
1	The sub-trees structure must match.
2	The sub-trees structure and the number of visits must match.
3	The structure of the call-path to MPI calls must match. Nodes that are not on an MPI call-path may differ.
4	Like Mode 3, but the number of visits of the MPI calls must match, too.
5	Like Mode 4, but the number of visits must match also match on all nodes on the call-path to an MPI function.

Clustering is a lossy compression mechanism. The accuracy increases if more clusters are available. On the downside, more clusters require more memory. You can specify the number of clusters you want by setting the environment variable `SCOREP_PROFILING_CLUSTER_COUNT` to the number of cluster you want to have. The default cluster number is 64.

Furthermore, you can enforce a minimal structural similarity of instances of a cluster. Clusters that fit the minimal structural similarity requirements belong to the same equivalence class. Only instances of the same equivalence class will be clustered together. If you have more equivalence classes than the number of clusters you specified in `SCOREP_PROFILING_CLUSTER_COUNT`, the maximal number of clusters is increased. Thus, you might get more clusters than you specified.

The minimal structural similarity is defined by the clustering mode which can be set via the environment variable `SCOREP_PROFILING_CLUSTERING_MODE`. The value of this variable is a number between 0 and 5, specifying one of the modes described in Table 4.1.

4.1.5 Enabling additional debug output on inconsistent profiles

If the Score-P profiling system detects inconsistencies during measurement, it stops recording the profile and prints an error message. Examples for reasons of an inconsistent profile are, if the nesting order of function entries and exits is broken, or events appear for an uninitialized thread. This might indicate an bug of the profile, but typically the cause is an erroneous instrumentation. E.g. if manual instrumentation is applied, but not all possible exit points of a function are instrumented.

In order to support debugging of manual instrumentation, or during the development of own automatic instrumentation techniques, the profile can write additional information about its current state in a textual form into a file. This output may contain the following information:

4.2 Tracing

- The current call stack of the failing thread
- The profile structure of the failing thread
- The complete profile structure

None of the three entries is guaranteed to appear in the output, it depends on the current state of the profile. It might not be possible to provide any output at all. Furthermore, the online representation of the profile structure may differ from the final profile structure.

You can enable this additional output by setting the environment variable `SCOREP_PROFILING_ENABLE_CORE_FILES` to `true`. Then, if the profile detects an inconsistency, it will write a core file into your measurement directory. If an inconsistent profile is detected on multiple locations, every location where an inconsistency is detected will write a core file. Thus, it is not recommended, to enable this feature for large scale runs.

4.2 Tracing

Score-P can write events to OTF2 traces. By setting the environment variable `SCOREP_ENABLE_TRACING`, you can control whether a trace is recorded. If the value is 0 or `false` no trace is recorded, if the value is non-zero or `true`, a trace is recorded. If the variable is not specified, Score-P records traces on default. After trace recording you will find the OTF2 anchor file, named `trace.otf2` in the experiment directory, along with the trace data.

4.3 Filtering

When automatic compiler instrumentation or automated source code instrumentation with PDT has been used to instrument user-level source-program routines, there are cases where measurement and associated analysis are degraded, e.g., by frequently-executed, small and/or generally uninteresting functions, methods and subroutines.

A measurement filtering capability is therefore supported for compiler instrumented regions, regions instrumented with Score-P user API and regions from OPARI2 instrumentation (see Section 3.6). Because PDT instrumentation (Section 3.8) inserts, Score-P user API instrumentation, those regions can be filtered, too. Regions can be filtered based on their region name (e.g., their function name) or based on the source file, in which they are defined.

A file that contains the filter definition can be specified via the environment variable `SCOREP_FILTERING_FILE`. If no filter definition file is specified, all in-

strumented regions are recorded. For filtered regions, the enter/exit events are not recorded in trace and profile.

The filter definition file can contain two blocks:

- One block defines filter rules for filtering regions based on the source files they are defined in.
- One filter block defined rules for region names.

When the filter rules are applied, the source file name filter is evaluated first. If a region is filtered because it appears in a filtered source file, it cannot be included by the function name filter. If a region was defined in a not-filtered source file, the region name filter is evaluated. This means, events for a region are not recorded if they are filtered by the source file filter or the region name filter. Events for a region are recorded if the region is neither filtered by the source file filter nor by the region name filter. If one of the both filter blocks is not specified, it is equivalent to an empty filter block.

Beside the two filter blocks, you may use comments in the filter definition file. Comments start with the character '#' and is terminated by a new line. You may use comments also inside the filter blocks. If a region name or source file name contains '#', you must escape it with a backslash.

4.3.1 Source File Name Filter Block

The filter block for source file names, must be enclosed by `SCOREP_FILE_NAMES_BEGIN` and `SCOREP_FILE_NAMES_END`. In between you can specify an arbitrary number of include and exclude rules which are evaluated in sequential order. At the beginning all source files are included. Source files that are excluded after all rules are evaluated, are filtered.

An exclude rule starts with the keyword `EXCLUDE` followed by one or multiple white-space separated source file names. Respectively, include rules start with `INCLUDE` followed by one or multiple white-space separated file names. For the specification of file names, bash-like wild-cards are supported. In particular, the '*' wild-card matches an string of arbitrary length, the '?' matches exactly one arbitrary character, or within '[' you may specify multiple options.

Note

Unlike bash, a '*' may match a string that contains slashes. E.g, you may use the '*' wild-card for path prefixes.

An example source file filter block could look like this:

4.3 Filtering

```
SCOREP_FILE_NAMES_BEGIN # This is a comment
    EXCLUDE */filtering/filter*
    INCLUDE */filter_test.c
SCOREP_FILE_NAMES_END
```

Note

The keywords (SCOREP_FILE_NAMES_BEGIN, SCOREP_FILE_NAMES_END, EXCLUDE, and INCLUDE) are case-sensitive.

The filtering is based on the filenames as seen by the measurement system. Depending on instrumentation method and compiler the actual filename may contain the absolute path, a relative path or no path at all. The instrumentation tool tries to create as much absolute paths as possible. Paths are simplified before comparison to a rule. E.g. it removes `path/./`, `/./` and multiple slashes. You may look up the actual filename in the resulting output of the measurement.

4.3.2 Region Name Filter Block

The filter block for the region names, must be enclosed by SCOREP_REGION_NAMES_BEGIN and SCOREP_REGION_NAMES_END. In between you can specify an arbitrary number of include and exclude rules which are evaluated in sequential order. At the beginning, all regions are included. Regions that are excluded after all rules are evaluated, are filtered.

Note

Regions that are defined in source files that are filtered, are excluded due to the source file filter. They cannot be included anymore by an include rule in the region filter block.

An exclude rule starts with the keyword EXCLUDE followed by one or multiple white-space separated region names. Respectively, include rules start with INCLUDE followed by one or multiple white-space separated expressions. For the specification of region names, bash-like wild-cards are supported. In particular, the '*' wild card matches an string of arbitrary length, the '?' matches exactly one arbitrary character, or within '[' you may specify multiple options.

An example region filter block could look like this:

```
SCOREP_REGION_NAMES_BEGIN
    EXCLUDE *
    INCLUDE bar foo
           baz
           main
SCOREP_REGION_NAMES_END
```

In this example, all but the functions `bar`, `foo`, `baz` and `main` are filtered.

The filtering is based on the region names as seen by the measurement system. Depending on instrumentation method and compiler the actual region name may be mangled, or decorated. Thus, you may want to inspect the profile to determine the name of a region inside the measurement system.

In some cases, the instrumentation provides mangled names, which are demangled by Score-P. In this cases, Score-P uses the demangled form for display in profile and trace definitions, and thus, the demangled form should be used in the filter file. However, The `MANGLED` keyword marks a filter rule to be applied on the mangled name, if a different mangled name is available. If no mangled name is available, the rule is applied on the displayed name instead. The `MANGLED` keyword must appear inside of an include rule or exclude rule. All patterns of the rule that follow the `MANGLED` keyword, are applied to the mangled name, if the mangled name is available.

In the following example, `foo` and `baz` are applied to the mangled name, while `bar` and `main` are applied on the displayed name.

```
SCOREP_REGION_NAMES_BEGIN
  EXCLUDE *
  INCLUDE bar MANGLED foo
          baz
  INCLUDE main
SCOREP_REGION_NAMES_END
```

The displayed name may also be mangled if no demangled form is available. It is not necessary to prepend rules with the `MANGLED` keyword if the displayed name is mangled, but only if a mangled name is available that differs from the displayed name.

Note

The keywords (e.g., `EXCLUDE`, `INCLUDE`, `SCOREP_REGION_NAMES_BEGIN`, `SCOREP_REGION_NAMES_END`, and `MANGLED` are case-sensitive.

4.4 Selective Recording

Score-P experiments record by default all events during the whole execution run. If tracing is enabled the event data will be collected in buffers on each process that must be adequately sized to store events from the entire execution.

Instrumented routines which are executed frequently, while only performing a small amount of work each time they are called, have an undesirable impact on measurement. The measurement overhead for such routines is large in comparison to the execution time of the uninstrumented routine, resulting in measurement dilation. Recording these events requires significant space and analysis takes

4.4 Selective Recording

longer with relatively little improvement in quality. Filtering can be employed during measurement (described in Section 4.3) to ignore events from compiler-instrumented routines or user-instrumented routines.

Another possibility is not to record the whole application run. In many cases, only parts of the application are of interest for analysis (e.g. a frequently performed calculation) while other parts are of less interest (e.g., initialization and finalization) for performance analysis. Or the calculation itself shows iterative behavior, where recording of one iteration would be sufficient for analysis. Restricting recording to one or multiple time intervals during measurement would reduce the required space and overhead. This approach is called selective recording.

Score-P provides two possibilities for selective recording.

- A configuration file can specify recorded regions. The entry and exit of those regions define an interval during which events are recorded.
- With user instrumentation, the recording can be manually switched on /off. (See Section 3.2).

Switching recording on or off, can result in inconsistent traces or profiles, if not applied with care. Especially, switching recording on/off manually via `SCOREP_RECORDING_ON` and `SCOREP_RECORDING_OFF` from the Score-P user instrumentation macros is not recommended. Inconsistent traces may result in errors or deadlocks during analysis, or show unusable data. The consistency is endangered if:

- OpenMP events are missing in one thread while other threads have them. Furthermore, the OpenMP parallel region events are required if any event inside a parallel region is recorded. To prevent inconsistencies from incomplete recording of OpenMP events, it is not possible to switch recording on/off from inside a parallel region
- MPI a communication is only recorded partially, e.g. if a send is missing, but the corresponding receive on another process is recorded. To ensure recording of complete communication is the responsibility of the user.
- enter/exit events are not correctly nested.

How recording can be controlled through Score-P macros which are inserted in the application's source code, is explained in Section 3.2. Thus, this section focuses on first possibility, where the user specify recorded regions via a configuration file. Selective recording affects tracing and profiling.

For selective recording, you can specify one or multiple traced regions. The recording is enabled when a recorded region is entered. If the region is exited, recording of events is switched off again. If a recorded region is called inside another

recorded region, thus, the recording is already enabled, it will not disable recording of it exits, but recording will be switched off, if all recorded regions are exited.

For recorded regions only regions from Score-P user instrumentation can be selected. If regions from other instrumentation methods are specified in the configuration file for selective recording, they are ignored.

For a recorded region, the recording can be restricted to certain executions of that region. Therefore, the enters for a recorded region are counted, and a particular execution can be specified by the number of its enter. If a recorded region is called recursively, the recording is only switched off, if the exit is reached, that corresponds to the enter that enabled recording.

The configuration file is a simple text file, where every line contains the name of exactly one region. Optionally, a comma-separated list of execution numbers or intervals of execution numbers can be specified. A configuration file could look like follows:

```
foo
bar 23:25, 50, 60:62
baz 1
```

This configuration file would record all executions of foo, the executions 23, 24, 25, 50, 60, 61, and 62 of bar, and the second (numbering starts with 0) execution of baz.

To apply the selective recording configuration file to a measurement run of your application, set the environment variable `SCOREP_SELECTIVE_CONFIG_FILE` to the configuration file and run your instrumented application. If `SCOREP_SELECTIVE_CONFIG_FILE` is empty, or the given file cannot be opened, the whole application run will be recorded (no selective recording will apply).

4.5 Trace Buffer Rewind

Introducing a long-term event-trace recording mode, the trace buffer rewind feature allows to discard the preceding section of the event trace at certain control points or phase markers. The live decision whether to keep or discard a section can depend on the presence or absence of certain behaviour patterns as well as on similarity or difference with other sections.

Based on user regions (see 3.2), three macros are given which control the rewind. These are:

```
// to define a local region handle based on the function
// SCOREP_USER_REGION_DEFINE( ... )
SCOREP_USER_REWIND_DEFINE( regionHandle )
// similar to SCOREP_USER_REGION_BEGIN( ... )
```

4.5 Trace Buffer Rewind

```
SCOREP_USER_REWIND_POINT( regionHandle, "name" )
// similar to SCOREP_USER_REGION_END( ... )
// w/ additional parameter to control the rewind (yes or no)
SCOREP_USER_REWIND_CHECK( regionHandle, boolean )
```

The user has to specify whether or not a rewind is requested with a boolean variable in the `SCOREP_USER_REWIND_CHECK` function. There are two different approaches what to do with the rewind region in the trace based on the boolean variable. If the boolean variable is true, the trace buffer will be reset to an old snapshot and after that rewind region enter and leave events will be written into the trace buffer to mark the presence of the trace buffer rewind. This rewind region then looks like a normal user-defined region in the trace. If the variable is false, than no events of the rewind region are written into the trace, so that the trace buffer looks like the user never instrumented the code w/ rewind regions. Trace buffer flushes have an impact on the rewind regions, i.e. if a flush occurs all previous stored rewind points (which are not "checked", i.e. the flush is in between the region) will be deleted and the `SCOREP_USER_REWIND_CHECK` function won't write the enter/leave events into the trace independently from the boolean variable. Wrong nested rewind regions are handled as follows:

```
SCOREP_USER_REWIND_POINT( point 1, ... );
... do stuff ...
SCOREP_USER_REWIND_POINT( point 2, ... );
... do stuff ...
SCOREP_USER_REWIND_CHECK( point 1, true );
... do stuff ...
SCOREP_USER_REWIND_CHECK( point 2, true );
```

The check for point 2 would corrupt the trace buffer, so point 2 would be deleted and ignored in the second check.

4.5.1 Selection of MPI Groups

The Message Passing Interface (MPI) adapter of Score-P supports the tracing of most of MPI's 300+ function calls. MPI defines a so-called 'profiling interface' that supports the provision of wrapper libraries that can easily interposed between the user application and the MPI library calls.

The general Score-P filtering mechanism is not applied to MPI functions. Instead, the user can decide whether event generation is turned on or off for a group of MPI functions, at start time of the application. These groups are the listed sub-modules of this adapter. Each module has a short string token that identifies this group. To activate event generation for a specific group, the user can specify a comma-separated list of tokens in the configuration variable `SCOREP_MPI_ENABLE_GROUPS`. Additionally, special tokens exist to ease the handling by the user. A

CHAPTER 4. APPLICATION MEASUREMENT

Token	Module
ALL	Activate all available modules
DEFAULT	Activate the configured default modules of CG, COLL, ENV, IO, P2P, RMA, TOPO, XNONBLOCK. This can be used to easily activate additional modules.
CG	Communicators and groups
COLL	Collective communication
ENV	Environmental management
ERR	Error handlers
EXT	External interfaces
IO	I/O
MISC	Miscellaneous
P2P	Point-to-point communication
RMA	One-sided communication
SPAWN	Process management interface (aka Spawn)
TOPO	Topology communicators
TYPE	MPI Datatypes
XNONBLOCK	Extended non-blocking communication events
XREQTEST	Test events for tests of uncompleted requests

complete list of available tokens that can be specified in the runtime configuration is listed below.

Note

Event generation in this context only relates to flow and transfer events. Tracking of communicators, groups, and other internal data is unaffected and always turned on.

Example:

```
SCOREP_MPI_ENABLE_GROUPS=ENV, P2P
```

This will enable event generation for environmental management, including `MPI_Init` and `MPI_Finalize`, as well as point-to-point communication, but will disable it for all other functions groups.

A shorthand to get event generation for all supported function calls is

```
SCOREP_MPI_ENABLE_GROUPS=ALL
```

4.6 Recording MPI Communicator Names

A shorthand to add a single group, e.g. `TYPE`, to the configured default is

```
SCOREP_MPI_ENABLE_GROUPS=DEFAULT,TYPE
```

A detailed overview of the MPI functions associated with each group can be found in [Appendix B](#).

A somehow special role plays the `XNONBLOCK` flag. This flag determines what kind of events are generated by non-blocking peer-to-peer MPI function calls. If `XNONBLOCK` is not set, an `OTF2_MPI_Send` event is created at the non-blocking send call and an `OTF2_MPI_Recv` event is recorded when a non-blocking receive request has completed. If `XNONBLOCK` is set, an `OTF2_Isend` event is recorded at the non-blocking send and an `OTF2_IsendComplete` event when the event was completed. Furthermore, on a non-blocking receive, it records an `OTF2_IRecvRequest` event. On request completion an `OTF2_IRecv` event is recorded. In both cases the group `P2P` must be enabled. Otherwise Score-P records no events for peer-to-peer communication functions.

4.6 Recording MPI Communicator Names

The measurement system tracks also the names of MPI communicators to easily identify them later in the analysis. This is done via the `MPI_Comm_set_name` call. But there are some restrictions. First, the name of a communicator is only recorded at the first call to `MPI_Comm_set_name` for this communicator. Later calls are ignored. Also this call is only honored when the call was made from the rank which is rank 0 in this communicator. Other calls from other ranks are ignored. And lastly the name will also be not recorded if the communicator has only one member.

4.7 Recording Performance Metrics

If Score-P has been built with performance metric support it is capable of recording performance counter information. To request the measurement of certain counters, the user is required to set individual environment variables. The user can leave these environment variables unset to indicate that no counters are requested. Requested counters will be recorded with every enter/exit event.

4.7.1 PAPI Hardware Performance Counters

Score-P provides the possibility to query hardware performance counters and include these metrics into the trace and/or profile. Score-P uses the [Performance](#)

[Application Programming Interface](#) (PAPI) to access hardware performance counters. Recording of PAPI performance counters is enabled by setting the environment variable [SCOREP_METRIC_PAPI](#) to a comma-separated list of counter names. Counter names can be any PAPI preset names or PAPI native counter names.

Example:

```
SCOREP_METRIC_PAPI=PAPI_FP_OPS,PAPI_L2_TCM
```

This will record the number of floating point instructions and level 2 cache misses. If any of the requested counters is not recognized, program execution will be aborted with an error message. The PAPI utility programs `papi_avail` and `papi_native_avail` report information about the counters available on the current platform.

If you want to change the separator used in the list of PAPI counter names, set the environment variable [SCOREP_METRIC_PAPI_SEP](#) to the desired character.

Note

In addition it is possible to specify metrics that will be recorded only by the initial thread of a process. Please use [SCOREP_METRIC_PAPI_PER_PROCESS](#) for that reason.

4.7.2 Resource Usage Counters

Besides PAPI, Resource Usage Counters can be recorded. These metrics use the Unix system call `getrusage` to provide information about consumed resources and operating system events such as user/system time, received signals, and number of page faults. The manual page of `getrusage` provides a list of resource usage counters. Please note that the availability of specific counters depends on the operating system.

You can enable recording of resource usage counters by setting the [SCOREP_METRIC_RUSAGE](#) environment variable. The variable should contain a comma-separated list of counter names.

Example:

```
SCOREP_METRIC_RUSAGE=ru_utime,ru_stime
```

This will record the consumed user time and system time. If any of the requested counters is not recognized, program execution will be aborted with an error message.

4.7 Recording Performance Metrics

Note

Please be aware of the scope of displayed resource usage statistics. Score-P records resource usage statistics for each individual thread, if the output while configuring your Score-P installation contains something like

```
RUSAGE_THREAD support: yes
```

Otherwise, the information displayed is valid for the whole process. That means, for multi-threaded programs the information is the sum of resources used by all threads in the process.

A shorthand to record all resource usage counters is

```
SCOREP_METRIC_RUSAGE=all
```

However, this is not recommended as most operating systems does not support all metrics.

If you want to change the separator used in the list of resource usage metrics, set the environment variable `SCOREP_METRIC_RUSAGE_SEP` to the desired character.

Example:

```
SCOREP_METRIC_RUSAGE_SEP=:
```

This indicates that counter names in the list are separated by colons.

Note

In addition it is possible to specify metrics that will be recorded only by the initial thread of a process. Please use `SCOREP_METRIC_RUSAGE_PER_PROCESS` for that reason.

4.7.3 Metric Plugins

Metric plugins extend the functionality of Score-P by providing additional counter as external libraries. The libraries are loaded when tracing or profiling your application. So there is no need to recompile your application or instrument it manually.

The small example of a synchronous metric plugin can be found in Appendix C. The commands to build the corresponding library of this plugin might look like:

```
gcc -c -fPIC hello_world.c \
    -o libHelloWorld.so.o `scorep-config --cppflags`
gcc -shared -Wl,-soname,libHelloWorld.so \
    -o libHelloWorld.so libHelloWorld.so.o
```

To enable a metric plugin, set the environment variable `SCOREP_METRIC_PLUGINS`. In the following example we want to use a plugin named `HelloWorld`. The corresponding was built as `libHelloWorld.so`. Furthermore, we select two counters `metric1` and `metric2` from the plugin. Make sure that the metric plugin library is placed in a directory which is part of `LD_LIBRARY_PATH`.

```
SCOREP_METRIC_PLUGINS=HelloWorld
SCOREP_METRIC_HELLOWORLD=metric1,metric2
```

4.8 CUDA Performance Measurement

If Score-P has been built with CUDA support it is capable of recording CUDA API function calls and GPU activities. The measurement is based on NVIDIA's **CUDA Profiling and Tool Interface (CUPTI)**, which is an integral part of the CUDA Toolkit since version 4.1.

Score-P can wrap the NVIDIA compiler (**scorep nvcc**) to instrument `.cu` files. If Score-P has been built with the Intel compiler an additional flag has to be added for instrumentation:

```
--compiler-bindir=<path-to-intel-compiler-command>
```

Otherwise the program will not be instrumented, as `nvcc` uses the GNU compiler by default.

Setting the environment variable `SCOREP_CUDA_ENABLE` to **yes** enables CUDA measurement. To enable a particular composition of CUDA measurement features the variable should contain a comma-separated list of the following CUDA measurement options:

<code>runtime</code>	= CUDA runtime API
<code>driver</code>	= CUDA driver API
<code>kernel</code>	= CUDA kernels
<code>kernel_serial</code>	= Serialized kernel recording
<code>kernel_counter</code>	= Fixed CUDA kernel metrics
<code>idle</code>	= GPU compute idle time
<code>pure_idle</code>	= GPU idle time (memory copies are not idle)
<code>memcpy</code>	= CUDA memory copies
<code>sync</code>	= Record implicit and explicit CUDA synchronization
<code>gpumemusage</code>	= Record CUDA memory (de)allocations as a counter
<code>references</code>	= Record references between CUDA activities
<code>flushatexit</code>	= Flush CUDA activity buffer at program exit
<code>yes/DEFAULT/1</code>	= "runtime, kernel, memcpy"
<code>no</code>	= Disable CUDA measurement (same as unset <code>SCOREP_CUDA_ENABLE</code>)

CUPTI uses an extra buffer to store its activity records. If the size of this buffer is too small, Score-P will print a warning about the current buffer size and the number

4.9 Online Access Interface

of dropped records. To avoid dropping of records increase the buffer size via the environment variable `SCOREP_CUDA_BUFFER` (default: 1M).

Since CUDA toolkit version 5.5 the chunk size for the CUPTI activity buffer can be specified via the environment variable `SCOREP_CUDA_BUFFER_CHUNK` (default: 8k). Buffer chunks are allocated whenever CUPTI requests a buffer (e.g. to record activities on a CUDA stream). `SCOREP_CUDA_BUFFER` specifies the upper bound of memory to be allocated for CUPTI activities. Therefore it should be a multiple of `SCOREP_CUDA_BUFFER_CHUNK`.

Note

Make sure to call `cudaDeviceReset()` or `cudaDeviceSynchronize()` before the exit of the program. Otherwise GPU activities might be missing in the trace.

For CUDA 5.5 there is an error in CUPTI buffer handling. The last activity in a CUPTI activity buffer (`SCOREP_CUDA_BUFFER_CHUNK`) gets lost, when the buffer is full. To avoid this issue specify `SCOREP_CUDA_BUFFER_CHUNK` as large as necessary to store all CUDA device activities until the CUDA device is synchronized with the host. In CUDA 6.0 this issue is fixed and CUPTI does not request buffers for individual streams any more.

Score-P supports CUDA monitoring since CUDA toolkit version 4.1. Make sure that the Score-P installation has configured CUDA support. The configure summary should contain the line:

```
CUDA support: yes
```

If not, for most systems it is sufficient to specify the CUDA toolkit directory at Score-P configuration time:

```
--with-libcudart=<path-to-cuda-toolkit-directory>
```

Otherwise check the configure help output to specify the location of the CUDA toolkit and CUPTI libraries and include files:

```
./configure --help=recursive | grep -E "(cuda|cupti)"
```

CUDA device and host activities can be filtered by name at runtime using the Score-P filter file (see Section 4.3). Filtering does not remove CUDA activities inserted by Score-P or CUDA data transfers inserted as RDMA events. If a kernel is filtered, no kernel launch properties activated in `SCOREP_CUDA_ENABLE` using `kernel_counter` are inserted for this kernel. GPU idle time is not affected by kernel filtering.

4.9 Online Access Interface

Online Access (OA) is an interface to the measurement system of Score-P allowing online analysis capable tools to configure and retrieve profile measurements remotely over sockets.

The Online Access interface implements a client-server paradigm, where Score-P acts as a server accepting connections from the remote tool. During the initialization, the OA module of the Score-P creates one socket for each application process. The network addresses and the ports of these sockets are published at the registry service and could be later queried by the remote tool. The hostname and the port of the registry service should be specified via the `SCOREP_ONLINEACCESS_REG_HOST` and `SCOREP_ONLINEACCESS_REG_PORT` environment variables, respectively. After publishing the socket addresses and ports, the OA module will accept connections. Once the connection is established the OA module will suspend the application execution and wait for requests. The format of the requests is plain text following the syntax below:

```
<request>           = <configuration>|<execution>|<retrieval>
<configuration>     = BEGINREQUESTS GLOBAL <request_type>
                     ENDREQUESTS
<request_type>      = MPI | EXECUTION_TIME |
                     METRIC <metric_specification>
<metric_specification> = PERISCOPE <periscope_metric_code> |
                     PAPI "<papi_counter_name>" |
                     RUSAGE "rusage_metric_name" |
                     OTHER "metric_name"
<execution>         = TERMINATE | RUNTOSTART | RUNTOEND
<retrieval>         = GETSUMMARYDATA
```

where

- `BEGINREQUESTS` indicates the beginning of the request list,
- `ENDREQUESTS` indicates the end of the request list,
- `GLOBAL` indicates that the following measurement request is applied to all locations,
- `MPI` requests mpi wait states analysis,
- `EXECUTION_TIME` requests execution time,
- `METRIC` indicates the begin of the metric request,
- `PERISCOPE <periscope_metric_code>` requests a metric by the Periscope internal code,
- `PAPI <papi_counter_name>` requests a a PAPI hardware counter metric by the counter name,
- `RUSAGE <rusage_counter_name>` requests a Resource Usage Counter metric by the counter name,

4.9 Online Access Interface

- OTHER `<metric_name>` requests a metric, to be defined in Score-P definition system, specified by the name,
- TERMINATE requests termination of the application,
- RUNTOSTART requests Score-P to run the beginning of the OA phase,
- RUNTOEND requests Score-P to run the end of the OA phase,
- GETSUMMARYDATA requests retrieval of the profile data.

When the GETSUMMARY request is received, the OA module will transform the call-path profile into a flat profile and send the data back to the remote tool. The flat profile is sent in two parts, where the first part carries the region definition data and the second part carries profile measurements. Each part starts with the key word MERGED_REGION_DEFINITIONS or FLAT_PROFILE and followed by the number of the entries and the buffer containing the data.

Chapter 5

Usage of scorep-score

scorep-score is a tool that allows to estimate the size of an OTF2 trace from a CUBE4 profile. Furthermore, the effects of filters are estimated. The main goal is to define appropriate filters for a tracing run from a profile.

The general work-flow for performance analysis with Score-P is:

1. Instrument an application (see Section [3](#)).
2. Perform a measurement run and record a profile (see Section [4](#)). The profile already gives an overview what may happen inside the application.
3. Use scorep-score to define an appropriate filter for an application. Otherwise the trace file may become too large. This step is explained in this Chapter.
4. Perform a measurement run with tracing enabled and the filter applied (see Section [4.2](#) and Section [4.3](#)).
5. Perform in-depth analysis on the trace data.

5.1 Basic usage

To invoke `scorep-score` you must provide the filename of a CUBE4 profile as argument. Thus, the basic command looks like this:

```
scorep-score profile.cubex
```

The output of the command may look like this (taking an MPI/OpenMP hybrid application as an example):

CHAPTER 5. USAGE OF SCOREP-SCORE

```
Estimated aggregate size of event trace:                20MB
Estimated requirements for largest trace buffer (max_buf): 20MB
Estimated memory requirements (SCOREP_TOTAL_MEMORY):    24MB
(hint: When tracing set SCOREP_TOTAL_MEMORY=24MB to avoid intermediate flushes
or reduce requirements using USR regions filters.)
```

flt	type	max_buf[B]	visits	time[s]	time[%]	time/visit[us]	region
	ALL	19,377,048	786,577	27.48	100.0	34.93	ALL
	USR	16,039,680	668,320	0.36	1.3	0.53	USR
	OMP	3,328,344	117,881	26.92	98.0	228.37	OMP
	COM	9,024	376	0.20	0.7	532.17	COM

The first line of the output gives an estimation of the total size of the trace, aggregated over all processes. This information is useful for estimating the space required on disk. In the given example, the estimated total size of the event trace is 20MB.

The second line prints an estimation of the memory space required by a single process for the trace. The memory space that Score-P reserves on each process at application start must be large enough to hold the process' trace in memory in order to avoid flushes during runtime, because flushes heavily disturb measurements. In addition to the trace, Score-P requires some additional memory to maintain internal data structures. Thus, it provides also an estimation for the total amount of required memory on each process. The memory size per process that Score-P reserves is set via the environment variable `SCOREP_TOTAL_MEMORY`. In the given example the per process memory should be larger than 24MB.

Beginning with the 6th line, `scorep-score` prints a table that show how the trace memory requirements and the runtime is distributed among certain function groups. The column `max_tbc` shows how much trace buffer is needed on a single process. The column `time(s)` shows how much execution time was spend in regions of that group in seconds, the column `%` shows the fraction of the overall runtime that was used by this group, and the column `time/visit(us)` shows the average time per visit in microseconds.

The following groups exist:

- **ALL:** Includes all functions of the application
- **OMP:** This group contains all regions that represent an OpenMP construct
- **MPI:** This group contains all MPI functions
- **SHMEM:** This group contains all SHMEM functions
- **COM:** This group contains all functions, implemented by the user that appear on a call-path to an OpenMP construct, or MPI/SHMEM function.
- **USR:** This group contains all user functions that do not appear on a call-path to an OpenMP construct, or MPI/SHMEM function.

5.2 Additional per-region information

5.2 Additional per-region information

For a more detailed output, which shows the data for every region, you can use the `-r` option. The command could look like this.

```
scorep-score profile.cubex -r
```

This command adds information about the used buffer sizes and execution time of every region to the table. The additional lines of the output may look like this:

flt	type	max_buf[B]	visits	time[s]	time[%]	time/visit[us]	region
	COM	24	4	0.00	0.0	67.78	Init
	COM	24	4	0.00	0.0	81.20	main
	USR	24	4	0.12	2.0	30931.14	InitializeMatr
	COM	24	4	0.05	0.8	12604.78	CheckError
	USR	24	4	0.00	0.0	23.76	PrintResults
	COM	24	4	0.01	0.2	3441.83	Finish
	COM	24	4	0.48	7.7	120338.17	Jacobi

The region name is displayed in the column named `region`. The column `type` shows to which group this region belongs. In the example above the function `main` belongs to group `COM` required 24 bytes per process and used 0 s execution time. The regions are sorted by their buffer requirements.

5.3 Defining and testing a filter

For defining a filter, it is recommended to exclude short frequently called functions from measurement, because they require a lot of buffer space (represented by a high value under `max_tbc`) but incur a high measurement overhead. Furthermore, for communication analysis, functions that appear on a call-path to MPI functions and OpenMP constructs (regions of type `COM`) are usually of more interest than user functions of type `USR` which do not appear on call-path to communications. MPI functions and OpenMP constructs cannot be filtered. Thus, it is usually a good approach to exclude regions of type `USR` starting at the top of the list until you reduced the trace to your needs. Section 4.3 describes the format of a filter specification file.

If you have a filter file, you can test the effect of your filter on the trace file. Therefore, you need to pass a `-f` followed by the file name of your filter. E.g. if your filter file name is `myfilter`, the command looks like this:

```
scorep-score profile.cubex -f myfilter
```

CHAPTER 5. USAGE OF SCOREP-SCORE

An example output is:

```
Estimated aggregate size of event trace:          7kB
Estimated requirements for largest trace buffer (max_buf): 1806 bytes
Estimated memory requirements (SCOREP_TOTAL_MEMORY): 5MB
(hint: When tracing set SCOREP_TOTAL_MEMORY=5MB to avoid intermediate flushes
or reduce requirements using USR regions filters.)
```

flt	type	max_buf[B]	visits	time[s]	time[%]	time/visit[us]	region
-	ALL	2,093	172	5.17	100.0	30066.64	ALL
-	MPI	1,805	124	4.20	81.3	33910.31	MPI
-	COM	240	40	0.84	16.3	21092.44	COM
-	USR	48	8	0.12	2.4	15360.71	USR
*	ALL	1,805	124	4.20	81.3	33910.31	ALL-FLT
-	MPI	1,805	124	4.20	81.3	33910.31	MPI-FLT
+	FLT	288	48	0.97	18.7	20137.15	FLT

Now, the output estimates the total trace size and the required memory per process, if you would apply the provided filter for the measurement run which records the trace. A new group `FLT` appears, which contains all regions that are filtered. Under `max_tbc` the group `FLT` displays how the memory requirements per process are reduced. Furthermore, the groups that end on `-FLT`, like `ALL-FLT` contain only the unfiltered regions of the original group. E.g. `USR-FLT` contains all regions of group `USR` that are not filtered.

Furthermore, the column `flt` is no longer empty but contains a symbol that indicates how this group is affected by the filter. A `'-'` means 'not filtered', a `'+'` means 'filtered' and a `'*'` appears in front of groups that potentially can be affected by the filter.

You may combine the `-f` option with a `-r` option. In this case, for each function a `'+'` or `'-'` indicates whether the function is filtered.

5.4 Calculating the effects of recording hardware counters

Recording additional metrics, e.g. hardware counters may significantly increase the trace size, because for many events additional metric values are stored. In order to estimate the effects of these metrics, you may add a `-c` followed by the number of metrics you want to record. E.g.

```
scorep-score profile.cubex -c 3
```

would mean that `scorep-score` estimates the disk and memory requirements for the case that you record 3 additional metrics.

Chapter 6

Performance Analysis Workflow Using Score-P

This chapter demonstrates a typical performance analysis workflow using Score-P. It consist of the following steps:

1. Program instrumentation (Section [6.1](#))
2. Summary measurement collection (Section [6.2](#))
3. Summary report examination (Section [6.3](#))
4. Summary experiment scoring (Section [6.4](#))
5. Advanced summary measurement collection (Section [6.5](#))
6. Advanced summary report examination (Section [6.6](#))
7. Event trace collection and examination (Section [6.7](#))

The workflow is demonstrated using NPB BT-MZ benchmark as an example. BT-MZ solves a discretized version of unsteady, compressible Navier-Stokes equations in three spatial dimensions. It performs 200 time-steps on a regular 3-dimensional grid using ADI and verifies solution error within acceptable limit. It uses intra-zone computation with OpenMP and inter-zone communication with MPI. The benchmark can be build with a predefined data class (S,W,A,B,C,D,E,F) and any number of MPI processes and OpenMP threads.

NPB BT-MZ distribution already prepared for this example could be obtained from [here](#).

CHAPTER 6. PERFORMANCE ANALYSIS WORKFLOW USING SCORE-P

6.1 Program Instrumentation

In order to collect performance measurements, BT-MZ has to be instrumented. There are various types of instrumentation supported by Score-P which cover a broad spectrum of performance analysis use cases (see Chapter 3 for more details).

In this example we start with automatic compiler instrumentation by prepending compiler/linker specification variable `MPIF77` found in `config/make.def` with `scorep`:

```
# SITE- AND/OR PLATFORM-SPECIFIC DEFINITIONS
#-----
# Items in this file may need to be changed for each platform.
#-----
...
#-----
# The Fortran compiler used for MPI programs
#-----
#MPIF77 = mpif77
# Alternative variants to perform instrumentation
...
MPIF77 = scorep mpif77
# This links MPI Fortran programs; usually the same as ${MPIF77}
FLINK   = $(MPIF77)
...
```

After the makefile is modified and saved, it is recommended to return to the root folder of the application and clean-up previously build files:

```
% make clean
```

Now the application is ready to be instrumented by simply issuing the standard build command:

```
% make bt-mz CLASS=W NPROCS=4
```

After the command is issued, the make command should produce the output similar to the one below:

```
cd BT-MZ; make CLASS=W NPROCS=4 VERSION=
make: Entering directory 'BT-MZ'
cd ../sys; cc -o setparams setparams.c -lm
../sys/setparams bt-mz 4 W
scorep mpif77 -c -O3 -fopenmp bt.f
[...]
cd ../common; scorep --user mpif77 -c -O3 -fopenmp timers.f
scorep mpif77 -O3 -fopenmp -o ../bin.scorep/bt-mz_W.4 \
```

6.2 Summary Measurement Collection

```
bt.o initialize.o exact_solution.o exact_rhs.o set_constants.o \
adi.o rhs.o zone_setup.o x_solve.o y_solve.o exch_qbc.o \
solve_subs.o z_solve.o add.o error.o verify.o mpi_setup.o \
../common/print_results.o ../common/timers.o
Built executable ../bin.scorep/bt-mz_W.4
make: Leaving directory 'BT-MZ'
```

When make finishes, the built and instrumented application could be found under `bin.scorep/bt-mz.4`.

6.2 Summary Measurement Collection

Now instrumented BT-MZ is ready to be executed and to be profiled by Score-P at the same time. However before doing so, one has an opportunity to configure Score-P measurement by setting Score-P environment variables. For the complete list of variables please refer to [Appendix E](#).

The typical Score-P performance analysis workflow implies collecting summary performance information first and then in detail performance exploration using execution traces. Therefore Score-P has to be configured to perform profiling and tracing has to be disabled. This is done by setting corresponding environment variables:

```
% export SCOREP_ENABLE_PROFILING=1
% export SCOREP_ENABLE_TRACING=0
```

Performance data collected by Score-P will be stored in an experiment directory. In order to efficiently manage multiple experiments, one can specify a meaningful name for the experiment directory by setting

```
% export SCOREP_EXPERIMENT_DIRECTORY=scorep_bt-mz_W_4x4_sum
```

After Score-P is prepared for summary collection, the instrumented application can be started as usual:

```
% cd bin.scorep
% export OM_NUM_THREADS=4
% mpiexec -np 4 ../bt-mz_W.4
```

The BT-MZ output should look similar to the listing below:

```
NAS Parallel Benchmarks (NPB3.3-MZ-MPI) BT-MZ MPI+OpenMP Benchmark

Number of zones:    4 x    4
Iterations: 200      dt:    0.000800
```

CHAPTER 6. PERFORMANCE ANALYSIS WORKFLOW USING SCORE-P

```
Number of active processes:      4

Use the default load factors with threads
Total number of threads:        16 ( 4.0 threads/process)

Calculated speedup =            15.78

Time step      1
[... More application output ...]
```

After application execution is finished, the summary performance data collected by Score-P is stored in the experiment directory `bin.scorep/scorep_bt-mz-W_4x4_sum`. The directory contains the following files:

- `scorep.cfg` - a record of the measurement configuration used in the run
- `profile.cubex` - the analysis report that was collated after measurement

6.3 Summary report examination

After BT-MZ finishes execution, the summary performance data measured by Score-P can be investigated with CUBE or ParaProf interactive report exploration tools.

CUBE:

```
% cube scorep_bt-mz_W_4x4_sum/profile.cubex
```

ParaProf:

```
% paraprof scorep_bt-mz_W_4x4_sum/profile.cubex
```

Both tools will reveal the call-path profile of BT-MZ annotated with metrics: *Time*, *Visits count*, MPI message statistics (bytes sent/received). For more information on using the tool please refer to the corresponding documentation ([CUBE](#), [ParaProf](#)).

6.4 Summary experiment scoring

Though we were able to collect the profile data, one can mention that the execution took longer in comparison to un-instrumented run, even when the time spent for measurement start-up/finalization is disregarded. Longer execution times of the instrumented application is a sign of high instrumentation/measurement overhead. Furthermore, this overhead might result in large trace files and buffer flushes in the later tracing experiment if Score-P is not properly configured.

6.4 Summary experiment scoring

In order to investigate sources of the overhead and to tune measurement configuration for consequent trace collection with Score-P, `scorep-score` tool (see Section 5 for more details about `scorep-score`) can be used:

```
% scorep-score scorep_bt-mz_W_4x4_sum/profile.cubex
Estimated aggregate size of event trace (total_tbc):
    990247448 bytes
Estimated requirements for largest trace buffer (max_tbc):
    256229936 bytes
(hint: When tracing set SCOREP_TOTAL_MEMORY > max_tbc to avoid
intermediate flushes
or reduce requirements using file listing names of USR regions
to be filtered.)
flt type      max_tbc      time      % region
  ALL      256229936      5549.78    100.0 ALL
  USR      253654608      1758.27     31.7 USR
  OMP       5853120      3508.57     63.2 OMP
  COM       343344       183.09      3.3 COM
  MPI        93776        99.86       1.8 MPI
```

The textual output of the tool generates an estimation of the size of an OTF2 trace produced, should Score-P be run using the current configuration. Here the trace size estimation could be also seen as a measure of overhead, since both are proportional to the number of recorded events. Additionally, the tool shows the distribution of the required trace size over call-path classes. From the report above one can see that the estimated trace size needed is equal to 1 GB in total or 256 MB per MPI rank, which is significant. From the breakdown per call-path class one can see that most of the overhead is due to user-level computations. In order to further localize the source of the overhead, `scorep-score` can print the breakdown of the buffer size on per-region basis:

```
% scorep-score -r scorep_bt-mz_W_4x4_sum/profile.cubex
[...]
flt type      max_tbc      time      % region
  ALL      256229936      5549.78    100.0 ALL
  USR      253654608      1758.27     31.7 USR
  OMP       5853120      3508.57     63.2 OMP
  COM       343344       183.09      3.3 COM
  MPI        93776        99.86       1.8 MPI
  USR       79176312      559.15     31.8 binvrhs_
  USR       79176312      532.73     30.3 matvec_sub_
  USR       79176312      532.18     30.3 matmul_sub_
  USR       7361424       50.51      2.9 binvrhs_
  USR       7361424       56.35      3.2 lhsinit_
  USR       3206688       27.32      1.6 exact_solution_
  OMP      1550400      1752.20     99.7 !$omp implicit barrier
  OMP       257280        0.44        0.0 !$omp parallel @exch_qbc.f
  OMP       257280        0.61        0.0 !$omp parallel @exch_qbc.f
  OMP       257280        0.48        0.0 !$omp parallel @exch_qbc.f
```

CHAPTER 6. PERFORMANCE ANALYSIS WORKFLOW USING SCORE-P

The regions marked as USR type contribute to around 32% of the total time, however, much of that is very likely to be measurement overhead due to frequently-executed small routines. Therefore, it is highly recommended to remove these routines from measurements. This can be achieved by placing them into a filter file (please refer to Section 5.3 for more details about filter file specification) as regions to be excluded from measurements. There is already a filter file prepared for BT-MZ which can be used:

```
% cat ../config/scorep.filt
SCOREP_REGION_NAMES_BEGIN EXCLUDE
binvcrhs*
matmul_sub*
matvec_sub*
exact_solution*
binvrhs*
lhs*init*
timer_*
```

One can use `scorep-score` once again to verify the effect of the filter file :

```
% scorep-score -f ../config/scorep.filt scorep_bt-mz_W_4x4_sum
Estimated aggregate size of event trace (total_tbc):
      20210360 bytes
Estimated requirements for largest trace buffer (max_tbc):
      6290888 bytes
(hint: When tracing set SCOREP_TOTAL_MEMORY > max_tbc to avoid
intermediate flushes
or reduce requirements using file listing names of USR regions
to be filtered.)
```

Now one can see that the trace size is reduced to just 20MB in total or 6MB per MPI rank. The regions filtered out will be marked with "+" in the left-most column of the per-region report.

6.5 Advanced summary measurement collection

After the filtering file is prepared to exclude the sources of the overhead, it is recommended to repeat summary collection, in order to obtain more precise measurements.

In order to specify the filter file to be used during measurements, the corresponding environment variable has to be set:

```
% export SCOREP_FILTERING_FILE=../config/scorep.filt
```

It is also recommended to adjust the experiment directory name for the new run:

6.5 Advanced summary measurement collection

```
% export SCOREP_EXPERIMENT_DIRECTORY=\
    scorep_bt-mz_W_4x4_sum_with_filter
```

Score-P also has a possibility to record hardware counters (see Section 4.7.1) and operating system resource usage (see Section 4.7.2) in addition to default time and number of visits metrics. Hardware counters could be configured by setting Score-P environment variable `SCOREP_METRIC_PAPI` to the comma-separated list of PAPI events (other separator could be specified by setting `SCOREP_METRIC_PAPI_SEP`):

```
% export SCOREP_METRIC_PAPI=PAPI_TOT_INS,PAPI_FP_INS
```

Note

The specified combination of the hardware events has to be valid, otherwise Score-P will abort execution. Please run `papi_aval` and `papi_native_aval` in order to get the list of the available PAPI generic and native events.

Operating system resource usage metrics are configured by setting the following variable:

```
% export SCOREP_METRIC_RUSAGE=ru_maxrss,ru_stime
```

Additionally Score-P can be configured to record only a subset of the mpi functions. This is achieved by setting `SCOREP_MPI_ENABLE_GROUPS` variable with a comma-separated list of sub-groups of MPI functions to be recorded (see Appendix B):

```
% export SCOREP_MPI_ENABLE_GROUPS=cg,coll,p2p,xnonblock
```

In case performance of the CUDA code is of interest, Score-P can be configured to measure CUPTI metrics as follows (see Section 4.8):

```
% export SCOREP_CUDA_ENABLE=gpu,kernel,idle
```

When the granularity offered by the automatic compiler instrumentation is not sufficient, one can use Score-P manual user instrumentation API (see Section 3.2) for more fine-grained annotation of particular code segments. For example initialization code, solver or any other code segment of interest can be annotated.

In order to enable user instrumentation, an `--user` argument has to be passed to Score-P command prepending compiler and linker specification:

```
% MPIF77 = scorep --user mpif77
```

CHAPTER 6. PERFORMANCE ANALYSIS WORKFLOW USING SCORE-P

Below, the loop found on line ... in file ... is annotated as a user region:

```
#include "scorep/SCOREP_User.inc"
subroutine foo(...)
  ! Declarations
  SCOREP_USER_REGION_DEFINE( solve )
  ! Some code...
  SCOREP_USER_REGION_BEGIN( solve, "<solver>", \
                           SCOREP_USER_REGION_TYPE_LOOP )

  do i=1,100
    [...]
  end do
  SCOREP_USER_REGION_END( solve )
  ! Some more code...
end subroutine
```

This will appear as an additional region in the report.

BT-MZ has to be recompiled and relinked in order to complete instrumentation.

```
% make clean
% make bt-mz CLASS=W NPROCS=4
```

After applying advanced configurations described above, summary collection with Score-P can be started as usual:

```
% mpiexec -np 4 ./bt-mz_W.4
```

6.6 Advanced summary report examination

After execution is finished, one can use `scorep-score` tool to verify the effect of filtering:

```
% scorep-score scorep_bt-mz_W_4x4_sum_with_filter/profile.cubex
Estimated aggregate size of event trace (total_tbc):
      20210360 bytes
Estimated requirements for largest trace buffer (max_tbc):
      6290888 bytes
(hint: When tracing set SCOREP_TOTAL_MEMORY > max_tbc to avoid
intermediate flushes
or reduce requirements using file listing names of USR regions
to be filtered.)
flt type      max_tbc      time      % region
  ALL      6290888      241.77    100.0 ALL
  OMP      5853120      168.94     69.9 OMP
  COM       343344       35.57     14.7 COM
  MPI       93776        37.25     15.4 MPI
  USR         672         0.01      0.0 USR
```

6.7 Event trace collection and examination

The report above shows significant reduction in runtime (due to elimination of the overhead) not only in USR regions but also in MPI/OMP regions as well.

Now, the extended summary report can be interactively explored using CUBE:

```
% cube scorep_bt-mz_W_4x4_sum_with_filter/profile.cubex
```

or ParaProf:

```
% paraprof scorep_bt-mz_W_4x4_sum_with_filter/profile.cubex
```

6.7 Event trace collection and examination

After exploring extended summary report, additional insight into performance of BT-MZ can be gained by performing trace collection. In order to do so, Score-P has to be configured to perform tracing by setting corresponding variable to `true` and disabling profile generation:

```
% export SCOREP_ENABLE_TRACING=true  
% export SCOREP_ENABLE_PROFILING=false
```

Additionally it is recommended to set a meaningful experiment directory name:

```
% export SCOREP_EXPERIMENT_DIRECTORY=scorep_bt-mz_W_4x4_trace
```

After BT-MZ execution is finished, a separate trace file per thread is written into the new experiment directory. In order to explore it, [Vampir](#) tool can be used:

```
% vampir scorep_bt-mz_W_4x4_trace/traces.otf2
```

Please consider that traces can become extremely large and unwieldy, because the size of the trace is proportional to number of processes/threads (width), duration (length) and detail (depth) of measurement. When the trace is too large to hold in the memory allocated by Score-P, flushes can happen. Unfortunately the resulting traces are of little value, since uncoordinated flushes result in cascades of distortion.

Traces should be written to a parallel file system, e.g., to `/work` or `/scratch` which are typically provided for this purpose.

Appendices

Appendix A

Score-P INSTALL

```
*
* This file is part of the Score-P software (http://www.score-p.org)
*
* Copyright (c) 2009-2013,
* RWTH Aachen University, Germany
*
* Copyright (c) 2009-2013,
* Gesellschaft fuer numerische Simulation mbH Braunschweig, Germany
*
* Copyright (c) 2009-2014,
* Technische Universitaet Dresden, Germany
*
* Copyright (c) 2009-2013,
* University of Oregon, Eugene, USA
*
* Copyright (c) 2009-2014,
* Forschungszentrum Juelich GmbH, Germany
*
* Copyright (c) 2009-2013,
* German Research School for Simulation Sciences GmbH, Juelich/Aachen, Germany
*
* Copyright (c) 2009-2013,
* Technische Universitaet Muenchen, Germany
*
* This software may be modified and distributed under the terms of
* a BSD-style license. See the COPYING file in the package base
* directory for details.
*
```

Score-P INSTALL GUIDE =====

This file describes how to configure, compile, and install the Score-P measurement infrastructure. If you are not familiar with using the configure scripts generated by GNU autoconf, read the "Generic

APPENDIX A. SCORE-P INSTALL

Installation Instructions" section below; then return here.

Quick start =====

In a nutshell, configuring, building, and installing Score-P can be as simple as executing the shell commands

```
./configure --prefix=<installdir>
make
make install
```

If you don't specify --prefix, /opt/scorep will be used.

Depending on your system configuration and specific needs, the build process can be customized as described below.

Note Score-P requires a case sensitive file system to build correctly.

Configuration =====

The configure script in this package tries to automatically determine the platform for which Score-P will be compiled in order to provide reasonable defaults for backend (i.e., compute-node) compilers, MPI compilers, and, in case of cross-compiling environments, frontend (i.e., login-node) compilers.

Depending on the environment it is possible to override the platform defaults by using the following configure options:

```
--with-machine-name=<default machine name>
    The default machine name used in profile and trace
    output. We suggest using a unique name, e.g., the
    fully qualified domain name. If not set, a name
    based on the detected platform is used. Can be
    overridden at measurement time by setting the
    environment variable SCOREP_MACHINE_NAME.
```

In non-cross-compiling environments, the compiler suite used to build the backend parts can be specified explicitly if desired. On Linux clusters it is currently recommended to use this option to select a compiler suite other than GCC.

```
--with-nocross-compiler-suite=(gcc|ibm|intel|pgi|studio)
    The compiler suite used to build this package in
    non-cross-compiling environments. Needs to be in $PATH.
    [Default: gcc]
```

In cross-compiling environments, the compiler suite used to build the frontend parts can be specified explicitly if desired.

```
--with-frontend-compiler-suite=(gcc|ibm|intel|pgi|studio)
    The compiler suite used to build the frontend parts of
    this package in cross-compiling environments. Needs to
    be in $PATH.
    [Default: gcc]
```

The MPI compiler, if in \$PATH, is usually autodetected. If there are several MPI compilers in \$PATH the user is requested to select one using the configure option:

```
--with-mpi=(bullxmpi|hp|ibmpoe|intel|intel2|intel3|intelpoe|lam| \
    mpibull2|mpich|mpich2|mpich3|openmpi|platform|scali| \
    sgimpt|sun)
    The MPI compiler suite to build this package in non
    cross-compiling mode. Usually autodetected. Needs to be
    in $PATH.
```

Note that there is currently no consistency check if backend and MPI compiler are from the same vendor. If they are not, linking problems (undefined references) might occur.

The SHMEM compiler, if in \$PATH, is usually autodetected. If there are several SHMEM compilers in \$PATH the user is requested to select one using the configure option:

```
--with-shmem=(openshmem|openmpi|sgimpt)
    The SHMEM compiler suite to build this package in
    non cross-compiling mode. Usually autodetected.
    Needs to be in $PATH.
```

If a particular system requires to use compilers different to those Score-P currently supports, please edit the three files vendor/common/build-config/platforms/platform-*-user-provided to your needs and use the following configure option:

```
--with-custom-compilers
    Customize compiler settings by 1. copying the three
    files
    <srcdir>/vendor/common/build-config/platforms/platform-*-user-provided
    to the directory where you run configure <builddir>,
    2. editing those files to your needs, and 3. running
    configure. Alternatively, edit the files under <srcdir>
    directly. Files in <builddir> take precedence. You are
    entering unsupported terrain. Namaste, and good luck!
```

On cross-compile systems the default frontend compiler is IBM XL for the Blue Gene series and GCC on all other platforms. The backend compilers will either be automatically selected by the platform detection (IBM Blue Gene series) or by the currently loaded environment modules (Cray XT series). If you want to customize these settings please use the configure option '--with-custom-compilers' as described above.

Although this package comes with recent versions of the OTF2 and CUBE4

APPENDIX A. SCORE-P INSTALL

writer libraries as well as the OPARI2 instrumenter included, it is possible to use existing installations instead. Here, the `--without` option means 'without external installation', i.e., the component provided with the tarball will be used:

```
--with-otf2[=<otf2-bindir>]
    Use an already installed and compatible OTF2 library
    (v1.4 or newer). Provide path to otf2-config.
    Auto-detected if already in $PATH.
--with-cube[=<cube-bindir>]
    Use an already installed and compatible CUBE4 library
    (v4.2 or newer). Provide path to cube-config.
    Auto-detected if already in $PATH.
--with-opari2[=<opari2-bindir>]
    Use an already installed and compatible OPARI2 (v.1.1
    or newer). Provide path to opari2-config.
    Auto-detected if already in $PATH.
```

For the components `otf2` and `opari2`, the corresponding `--without-<component>` or `--with-<component>=no` options will ignore the `<component>-config` in `$PATH` but use the Score-P internal components.

Options to further specify which features and external packages should be used to build Score-P are as follows:

```
--enable-debug          activate internal debug output [no]
--enable-shared[=PKGS]  build shared libraries [default=no]
--enable-static[=PKGS]  build static libraries [default=yes]
--enable-backend-test-runs
    Enable execution of tests during 'make check' [no]
    (does not affect building of tests, though). If
    disabled, the files 'check-file-*' and/or
    'skipped_tests' listing the tests are generated in the
    corresponding build directory.
--enable-cuda
    Enable or disable support for CUDA. Fail if support
    can't be satisfied but was requested.
--enable-timer-bgl_rts_get_timebase
    enable bgl_rts_get_timebase timer if available instead
    of platform default
--enable-timer-bgq_mftb
    enable bgq_mftb timer if available instead of platform
    default
--enable-timer-bgp_get_timebase
    enable bgp_get_timebase timer if available instead of
    platform default
--enable-timer-clock_gettime
    enable clock_gettime timer if available
    [Default on Linux platforms]
--enable-timer-cycle_counter_tsc
    enable cycle_counter_tsc timer if available instead of
    platform default
--enable-timer-gettimeofday
    enable gettimeofday timer if available instead of
```

```

        platform default
--enable-timer-ibm_realtime
        enable ibm_realtime timer if available instead of
        platform default
--enable-timer-intel_mmtimer
        enable intel_mmtimer timer if available instead of
        platform default
--enable-timer-papi_real_cyc
        enable papi_real_cyc timer if available instead of
        platform default
--enable-timer-papi_real_usec
        enable papi_real_usec timer if available instead of
        platform default
--with-pdt=<path-to-binaries>
        Specifies the path to the program database toolkit
        (PDT) binaries, e.g., cparse.
--with-extra-instrumentation-flags=flags
        Add additional instrumentation flags.
--with-sionlib[=<sionlib-bindir>]
        Use an already installed sionlib. Provide path to
        sionconfig. Auto-detected if already in $PATH. This
        option is not used by Score-P itself but passed to an
        internal OTF2.
--with-papi-header=<path-to-papi.h>
        If papi.h is not installed in the default location,
        specify the dirname where it can be found.
--with-papi-lib=<path-to-libpapi.*>
        If libpapi.* is not installed in the default location,
        specify the dirname where it can be found.
--with-libcudart=<Path to libcudart installation>
        If you want to build scorep with libcudart but do not
        have a libcudart in a standard location then you need
        to explicitly specify the directory where it is
        installed. On non-cross-compile systems we search the
        system include and lib paths per default [yes], on
        cross-compile systems however, you have to specify a
        path [no]. --with-libcudart is a shorthand for
        --with-libcudart-include=<Path/include> and
        --with-libcudart-lib=<Path/lib>. If these shorthand
        assumptions are not correct, you can use the explicit
        include and lib options directly.
--with-libcudart-include=<Path to libcudart headers>
--with-libcudart-lib=<Path to libcudart libraries>
--with-libcuda=<Path to libcuda installation>
        Usually not needed, specifying --with-libcudart should
        be fine!
        If you want to build scorep with libcuda but do not
        have a libcuda in a standard location then you need to
        explicitly specify the directory where it is
        installed. On non-cross-compile systems we search the
        system include and lib paths per default [yes], on
        cross-compile systems however, you have to specify a
        path [no]. --with-libcuda is a shorthand for
        --with-libcuda-include=<Path/include> and

```

APPENDIX A. SCORE-P INSTALL

```
--with-libcuda-lib=<Path/lib>. If these shorthand
assumptions are not correct, you can use the explicit
include and lib options directly.
--with-libcuda-include=<Path to libcuda headers>
--with-libcuda-lib=<Path to libcuda libraries>
--with-libcupti=(yes|no|<Path to libcupti installation>)
    If you want to build with libcupti support but do
    not have a libcupti in a standard location, you need
    to explicitly specify the directory where it is
    installed. On non-cross-compile systems we search
    the system include and lib paths per default [yes];
    on cross-compile systems, however, you have to
    specify a path [no]. --with-libcupti is a shorthand
    for --with-libcupti-include=<Path/include> and
    --with-libcupti-lib=<Path/lib>. If these shorthand
    assumptions are not correct, you can use the
    explicit include and lib options directly.
--with-libcupti-include=<Path to libcupti headers>
--with-libcupti-lib=<Path to libcupti libraries>
--with-libpmi=(yes|no|<Path to libpmi installation>)
    If you want to build with libpmi support but do not
    have a libpmi in a standard location, you need to
    explicitly specify the directory where it is
    installed. On non-cross-compile systems we search
    the system include and lib paths per default [yes];
    on cross-compile systems, however, you have to
    specify a path [no]. --with-libpmi is a shorthand
    for --with-libpmi-include=<Path/include> and
    --with-libpmi-lib=<Path/lib>. If these shorthand
    assumptions are not correct, you can use the
    explicit include and lib options directly.
--with-libpmi-include=<Path to libpmi headers>
--with-libpmi-lib=<Path to libpmi libraries>
--with-librca=(yes|no|<Path to librca installation>)
    If you want to build with librca support but do not
    have a librca in a standard location, you need to
    explicitly specify the directory where it is
    installed. On non-cross-compile systems we search
    the system include and lib paths per default [yes];
    on cross-compile systems, however, you have to
    specify a path [no]. --with-librca is a shorthand
    for --with-librca-include=<Path/include> and
    --with-librca-lib=<Path/lib>. If these shorthand
    assumptions are not correct, you can use the
    explicit include and lib options directly.
--with-librca-include=<Path to librca headers>
--with-librca-lib=<Path to librca libraries>
--with-libbfd=<Path to libbfd installation>
    If you want to build scorep with libbfd but do not have
    a libbfd in a standard location then you need to
    explicitly specify the directory where it is
    installed. On non-cross-compile systems we search the
    system include and lib paths per default [yes], on
    cross-compile systems however, you have to specify a
```

```

        path [no]. --with-libbfd is a shorthand for
        --with-libbfd-include=<Path/include> and
        --with-libbfd-lib=<Path/lib>. If these shorthand
        assumptions are not correct, you can use the explicit
        include and lib options directly.
--with-libbfd-include=<Path to libbfd headers>
--with-libbfd-lib=<Path to libbfd libraries>

```

Instead of passing command-line options to the 'configure' script, the package configuration can also be influenced by setting the following environment variables:

```

CC          C compiler command
CFLAGS      C compiler flags
LDFLAGS     linker flags, e.g. -L<lib dir> if you have libraries in a
            nonstandard directory <lib dir>
LIBS        libraries to pass to the linker, e.g. -l<library>
CPPFLAGS    (Objective) C/C++ preprocessor flags, e.g. -I<include dir> if
            you have headers in a nonstandard directory <include dir>
CPP         C preprocessor
CXX         C++ compiler command
CXXFLAGS    C++ compiler flags
CXXCPP      C++ preprocessor
CCAS        assembler compiler command (defaults to CC)
CCASFLAGS   assembler compiler flags (defaults to CFLAGS)
CXXCPP      C++ preprocessor
F77         Fortran 77 compiler command
FFLAGS      Fortran 77 compiler flags
FC          Fortran compiler command
FCFLAGS     Fortran compiler flags
CC_FOR_BUILD
            C compiler command for the frontend build
CXX_FOR_BUILD
            C++ compiler command for the frontend build
F77_FOR_BUILD
            Fortran 77 compiler command for the frontend build
FC_FOR_BUILD
            Fortran compiler command for the frontend build
CPPFLAGS_FOR_BUILD
            (Objective) C/C++ preprocessor flags for the frontend build,
            e.g. -I<include dir> if you have headers in a nonstandard
            directory <include dir>
CFLAGS_FOR_BUILD
            C compiler flags for the frontend build
CXXFLAGS_FOR_BUILD
            C++ compiler flags for the frontend build
FFLAGS_FOR_BUILD
            Fortran 77 compiler flags for the frontend build
FCFLAGS_FOR_BUILD
            Fortran compiler flags for the frontend build
LDFLAGS_FOR_BUILD
            linker flags for the frontend build, e.g. -L<lib dir> if you
            have libraries in a nonstandard directory <lib dir>
LIBS_FOR_BUILD

```

APPENDIX A. SCORE-P INSTALL

libraries to pass to the linker for the frontend build, e.g.
-l<library>

MPICC MPI C compiler command

MPICXX MPI C++ compiler command

MPIF77 MPI Fortran 77 compiler command

MPIFC MPI Fortran compiler command

MPI_CPPFLAGS MPI (Objective) C/C++ preprocessor flags, e.g. -I<include dir>
if you have headers in a nonstandard directory <include dir>

MPI_CFLAGS MPI C compiler flags

MPI_CXXFLAGS MPI C++ compiler flags

MPI_FFLAGS MPI Fortran 77 compiler flags

MPI_FCFLAGS MPI Fortran compiler flags

MPI_LDFLAGS MPI linker flags, e.g. -L<lib dir> if you have libraries in a
nonstandard directory <lib dir>

MPI_LIBS MPI libraries to pass to the linker, e.g. -l<library>

YACC The 'Yet Another Compiler Compiler' implementation to use.
Defaults to the first program found out of: 'bison -y', 'byacc',
'yacc'.

YFLAGS The list of arguments that will be passed by default to \$YACC.
This script will default YFLAGS to the empty string to avoid a
default value of '-d' given by some make applications.

RUNTIME_MANAGEMENT_TIMINGS Whether to activate time measurements for Score-P's
SCOREP_InitMeasurement() and scorep_finalize() functions.
Activation values are '1', 'yes', and 'true'. For developer use.

PAPI_INC Include path to the papi.h header.

PAPI_LIB Library path to the papi library.

LIBCUDART_INCLUDE Path to libcudart headers.

LIBCUDART_LIB Path to libcudart libraries.

LIBCUDA_INCLUDE Path to libcuda headers.

LIBCUDA_LIB Path to libcuda libraries.

LIBBFD_INCLUDE Path to libbfd headers.

LIBBFD_LIB Path to libbfd libraries.

Building & Installing

=====

Before building Score-P, carefully check whether the configuration summary printed by the configure script matches your expectations (i.e., whether MPI and/or OpenMP support is correctly enabled/disabled, external libraries are used, etc). If everything is OK, Score-P can be built and installed using

```
make
make install
```

Note that parallel builds (i.e., using 'make -j <n>') are fully supported.

Generic Installation Instructions

=====

Copyright (C) 1994, 1995, 1996, 1999, 2000, 2001, 2002, 2004, 2005,
2006, 2007, 2008, 2009 Free Software Foundation, Inc.

Copying and distribution of this file, with or without modification,
are permitted in any medium without royalty provided the copyright
notice and this notice are preserved. This file is offered as-is,
without warranty of any kind.

Basic Installation

=====

Briefly, the shell commands `./configure; make; make install` should
configure, build, and install this package. The following more-detailed
instructions are generic; see the section above for instructions
specific to this package. Some packages provide this `INSTALL` file but
do not implement all of the features documented below. The lack of an
optional feature in a given package is not necessarily a bug.

The `'configure'` shell script attempts to guess correct values for
various system-dependent variables used during compilation. It uses
those values to create a `'Makefile'` in each directory of the package.
It may also create one or more `'.h'` files containing system-dependent
definitions. Finally, it creates a shell script `'config.status'` that
you can run in the future to recreate the current configuration, and a
file `'config.log'` containing compiler output (useful mainly for
debugging `'configure'`).

It can also use an optional file (typically called `'config.cache'`
and enabled with `'--cache-file=config.cache'` or simply `'-C'`) that saves
the results of its tests to speed up reconfiguring. Caching is
disabled by default to prevent problems with accidental use of stale
cache files.

If you need to do unusual things to compile the package, please try
to figure out how `'configure'` could check whether to do them, and mail
diffs or instructions to support@score-p.org so they can be considered
for the next release. If you are using the cache, and at some point
`'config.cache'` contains results you don't want to keep, you may remove
or edit it.

The file `'configure.ac'` (or `'configure.in'`) is used to create
`'configure'` by a program called `'autoconf'`. You need `'configure.ac'` if
you want to change it or regenerate `'configure'` using a newer version
of `'autoconf'`.

The simplest way to compile this package is:

APPENDIX A. SCORE-P INSTALL

1. `'cd'` to the directory containing the package's source code and type `'./configure'` to configure the package for your system.

Running `'configure'` might take a while. While running, it prints some messages telling which features it is checking for.

2. Type `'make'` to compile the package.
3. Optionally, type `'make check'` to run any self-tests that come with the package, generally using the just-built uninstalled binaries.
4. Type `'make install'` to install the programs and any data files and documentation. When installing into a prefix owned by root, it is recommended that the package be configured and built as a regular user, and only the `'make install'` phase executed with root privileges.
5. Optionally, type `'make installcheck'` to repeat any self-tests, but this time using the binaries in their final installed location. This target does not install anything. Running this target as a regular user, particularly if the prior `'make install'` required root privileges, verifies that the installation completed correctly.
6. You can remove the program binaries and object files from the source code directory by typing `'make clean'`. To also remove the files that `'configure'` created (so you can compile the package for a different kind of computer), type `'make distclean'`. There is also a `'make maintainer-clean'` target, but that is intended mainly for the package's developers. If you use it, you may have to get all sorts of other programs in order to regenerate files that came with the distribution.
7. Often, you can also type `'make uninstall'` to remove the installed files again. In practice, not all packages have tested that uninstallation works correctly, even though it is required by the GNU Coding Standards.
8. Some packages, particularly those that use Automake, provide `'make distcheck'`, which can be used by developers to test that all other targets like `'make install'` and `'make uninstall'` work correctly. This target is generally not run by end users.

Compilers and Options

=====

Some systems require unusual options for compilation or linking that the `'configure'` script does not know about. Run `'./configure --help'` for details on some of the pertinent environment variables.

You can give `'configure'` initial values for configuration parameters by setting variables in the command line or in the environment. Here is an example:

```
./configure CC=c99 CFLAGS=-g LIBS=-lposix
```

*Note Defining Variables::, for more details.

Compiling For Multiple Architectures

=====

You can compile the package for more than one kind of computer at the same time, by placing the object files for each architecture in their own directory. To do this, you can use GNU 'make'. 'cd' to the directory where you want the object files and executables to go and run the 'configure' script. 'configure' automatically checks for the source code in the directory that 'configure' is in and in '..'. This is known as a "VPATH" build.

With a non-GNU 'make', it is safer to compile the package for one architecture at a time in the source code directory. After you have installed the package for one architecture, use 'make distclean' before reconfiguring for another architecture.

On MacOS X 10.5 and later systems, you can create libraries and executables that work on multiple system types--known as "fat" or "universal" binaries--by specifying multiple '-arch' options to the compiler but only a single '-arch' option to the preprocessor. Like this:

```
./configure CC="gcc -arch i386 -arch x86_64 -arch ppc -arch ppc64" \  
CXX="g++ -arch i386 -arch x86_64 -arch ppc -arch ppc64" \  
CPP="gcc -E" CXXCPP="g++ -E"
```

This is not guaranteed to produce working output in all cases, you may have to build one architecture at a time and combine the results using the 'lipo' tool if you have problems.

Installation Names

=====

By default, 'make install' installs the package's commands under '/usr/local/bin', include files under '/usr/local/include', etc. You can specify an installation prefix other than '/usr/local' by giving 'configure' the option '--prefix=PREFIX', where PREFIX must be an absolute file name.

You can specify separate installation prefixes for architecture-specific files and architecture-independent files. If you pass the option '--exec-prefix=PREFIX' to 'configure', the package uses PREFIX as the prefix for installing programs and libraries. Documentation and other data files still use the regular prefix.

In addition, if you use an unusual directory layout you can give options like '--bindir=DIR' to specify different values for particular kinds of files. Run 'configure --help' for a list of the directories you can set and what kinds of files go in them. In general, the default for these options is expressed in terms of '\${prefix}', so that

APPENDIX A. SCORE-P INSTALL

specifying just `--prefix` will affect all of the other directory specifications that were not explicitly provided.

The most portable way to affect installation locations is to pass the correct locations to `configure`; however, many packages provide one or both of the following shortcuts of passing variable assignments to the `make install` command line to change installation locations without having to reconfigure or recompile.

The first method involves providing an override variable for each affected directory. For example, `make install prefix=/alternate/directory` will choose an alternate location for all directory configuration variables that were expressed in terms of `${prefix}`. Any directories that were specified during `configure`, but not in terms of `${prefix}`, must each be overridden at install time for the entire installation to be relocated. The approach of makefile variable overrides for each directory variable is required by the GNU Coding Standards, and ideally causes no recompilation. However, some platforms have known limitations with the semantics of shared libraries that end up requiring recompilation when using this method, particularly noticeable in packages that use GNU Libtool.

The second method involves providing the `DESTDIR` variable. For example, `make install DESTDIR=/alternate/directory` will prepend `/alternate/directory` before all installation names. The approach of `DESTDIR` overrides is not required by the GNU Coding Standards, and does not work on platforms that have drive letters. On the other hand, it does better at avoiding recompilation issues, and works well even when some directory options were not specified in terms of `${prefix}` at `configure` time.

Optional Features =====

If the package supports it, you can cause programs to be installed with an extra prefix or suffix on their names by giving `configure` the option `--program-prefix=PREFIX` or `--program-suffix=SUFFIX`.

Some packages pay attention to `--enable-FEATURE` options to `configure`, where `FEATURE` indicates an optional part of the package. They may also pay attention to `--with-PACKAGE` options, where `PACKAGE` is something like `gnu-as` or `x` (for the X Window System).

For packages that use the X Window System, `configure` can usually find the X include and library files automatically, but if it doesn't, you can use the `configure` options `--x-includes=DIR` and `--x-libraries=DIR` to specify their locations.

Some packages offer the ability to configure how verbose the execution of `make` will be. For these packages, running `./configure --enable-silent-rules` sets the default to minimal output, which can be overridden with `make V=1`; while running `./configure --disable-silent-rules` sets the default to verbose, which can be overridden with `make V=0`.

Particular systems =====

On HP-UX, the default C compiler is not ANSI C compatible. If GNU CC is not installed, it is recommended to use the following options in order to use an ANSI C compiler:

```
./configure CC="cc -Ae -D_XOPEN_SOURCE=500"
```

and if that doesn't work, install pre-built binaries of GCC for HP-UX.

On OSF/1 a.k.a. Tru64, some versions of the default C compiler cannot parse its '<wchar.h>' header file. The option '-nodtk' can be used as a workaround. If GNU CC is not installed, it is therefore recommended to try

```
./configure CC="cc"
```

and if that doesn't work, try

```
./configure CC="cc -nodtk"
```

On Solaris, don't put '/usr/ucb' early in your 'PATH'. This directory contains several dysfunctional programs; working variants of these programs are available in '/usr/bin'. So, if you need '/usr/ucb' in your 'PATH', put it after '/usr/bin'.

On Haiku, software installed for all users goes in '/boot/common', not '/usr/local'. It is recommended to use the following options:

```
./configure --prefix=/boot/common
```

Specifying the System Type =====

There may be some features 'configure' cannot figure out automatically, but needs to determine by the type of machine the package will run on. Usually, assuming the package is built to be run on the same architectures, 'configure' can figure that out, but if it prints a message saying it cannot guess the machine type, give it the '--build=TYPE' option. TYPE can either be a short name for the system type, such as 'sun4', or a canonical name which has the form:

```
CPU-COMPANY-SYSTEM
```

where SYSTEM can have one of these forms:

```
OS  
KERNEL-OS
```

See the file 'config.sub' for the possible values of each field. If 'config.sub' isn't included in this package, then this package doesn't need to know the machine type.

APPENDIX A. SCORE-P INSTALL

If you are building compiler tools for cross-compiling, you should use the option `--target=TYPE` to select the type of system they will produce code for.

If you want to use a cross compiler, that generates code for a platform different from the build platform, you should specify the "host" platform (i.e., that on which the generated programs will eventually be run) with `--host=TYPE`.

Sharing Defaults

=====

If you want to set default values for `'configure'` scripts to share, you can create a site shell script called `'config.site'` that gives default values for variables like `'CC'`, `'cache_file'`, and `'prefix'`. `'configure'` looks for `'PREFIX/share/config.site'` if it exists, then `'PREFIX/etc/config.site'` if it exists. Or, you can set the `'CONFIG_SITE'` environment variable to the location of the site script. A warning: not all `'configure'` scripts look for a site script.

Defining Variables

=====

Variables not defined in a site shell script can be set in the environment passed to `'configure'`. However, some packages may run `'configure'` again during the build, and the customized values of these variables may be lost. In order to avoid this problem, you should set them in the `'configure'` command line, using `'VAR=value'`. For example:

```
./configure CC=/usr/local2/bin/gcc
```

causes the specified `'gcc'` to be used as the C compiler (unless it is overridden in the site shell script).

Unfortunately, this technique does not work for `'CONFIG_SHELL'` due to an Autoconf bug. Until the bug is fixed you can use this workaround:

```
CONFIG_SHELL=/bin/bash /bin/bash ./configure CONFIG_SHELL=/bin/bash
```

`'configure'` Invocation

=====

`'configure'` recognizes the following options to control how it operates.

`--help'`

`'-h'`

Print a summary of all of the options to `'configure'`, and exit.

`--help=short'`

`--help=recursive'`

Print a summary of the options unique to this package's

`'configure'`, and exit. The `'short'` variant lists options used

only in the top level, while the 'recursive' variant lists options also present in any nested packages.

'--version'
'-V'
Print the version of Autoconf used to generate the 'configure' script, and exit.

'--cache-file=FILE'
Enable the cache: use and save the results of the tests in FILE, traditionally 'config.cache'. FILE defaults to '/dev/null' to disable caching.

'--config-cache'
'-C'
Alias for '--cache-file=config.cache'.

'--quiet'
'--silent'
'-q'
Do not print messages saying which checks are being made. To suppress all normal output, redirect it to '/dev/null' (any error messages will still be shown).

'--srcdir=DIR'
Look for the package's source code in directory DIR. Usually 'configure' can determine that directory automatically.

'--prefix=DIR'
Use DIR as the installation prefix. *note Installation Names:: for more details, including other options available for fine-tuning the installation locations.

'--no-create'
'-n'
Run the configure checks, but stop before creating any output files.

'configure' also accepts some other, not widely useful, options. Run 'configure --help' for more details.

Appendix B

MPI wrapper affiliation

Some wrapper functions are affiliated with a function group that has not been described for direct user access in section 4.5.1. These groups are subgroups that contain function calls that are only enabled when both main groups are enabled. The reason for this is to control the amount of events generated during measurement, a user might want to turn off the measurement of non-critical function calls before the measurement of the complete main group is turned off. Subgroups can either be related to `MISC` (miscellaneous functions, e.g. handle conversion), `EXT` (external interfaces, e.g. handle attributes), or `ERR` (error handlers).

For example, the functions in group `CG_MISC` will only generate events if both groups `CG` and `MISC` are enabled at runtime.

B.1 Function to group

Function	Group
<code>MPI_Abort</code>	<code>EXT</code>
<code>MPI_Accumulate</code>	<code>RMA</code>
<code>MPI_Add_error_class</code>	<code>ERR</code>
<code>MPI_Add_error_code</code>	<code>ERR</code>
<code>MPI_Add_error_string</code>	<code>ERR</code>
<code>MPI_Address</code>	<code>MISC</code>
<code>MPI_Allgather</code>	<code>COLL</code>
<code>MPI_Allgatherv</code>	<code>COLL</code>
<code>MPI_Alloc_mem</code>	<code>MISC</code>
<code>MPI_Allreduce</code>	<code>COLL</code>
<code>MPI_Alltoall</code>	<code>COLL</code>

APPENDIX B. MPI WRAPPER AFFILIATION

MPI_Alltoallv	COLL
MPI_Alltoallw	COLL
MPI_Attr_delete	CG_EXT
MPI_Attr_get	CG_EXT
MPI_Attr_put	CG_EXT
MPI_Barrier	COLL
MPI_Bcast	COLL
MPI_Bsend	P2P
MPI_Bsend_init	P2P
MPI_Buffer_attach	P2P
MPI_Buffer_detach	P2P
MPI_Cancel	P2P
MPI_Cart_coords	TOPO
MPI_Cart_create	TOPO
MPI_Cart_get	TOPO
MPI_Cart_map	TOPO
MPI_Cart_rank	TOPO
MPI_Cart_shift	TOPO
MPI_Cart_sub	TOPO
MPI_Cartdim_get	TOPO
MPI_Close_port	SPAWN
MPI_Comm_accept	SPAWN
MPI_Comm_c2f	CG_MISC
MPI_Comm_call_errhandler	CG_ERR
MPI_Comm_compare	CG
MPI_Comm_connect	SPAWN
MPI_Comm_create	CG
MPI_Comm_create_errhandler	CG_ERR
MPI_Comm_create_keyval	CG_EXT
MPI_Comm_delete_attr	CG_EXT
MPI_Comm_disconnect	SPAWN
MPI_Comm_dup	CG
MPI_Comm_f2c	CG_MISC
MPI_Comm_free	CG
MPI_Comm_free_keyval	CG_EXT
MPI_Comm_get_attr	CG_EXT
MPI_Comm_get_errhandler	CG_ERR
MPI_Comm_get_name	CG_EXT
MPI_Comm_get_parent	SPAWN

B.1 Function to group

MPI_Comm_group	CG
MPI_Comm_join	SPAWN
MPI_Comm_rank	CG
MPI_Comm_remote_group	CG
MPI_Comm_remote_size	CG
MPI_Comm_set_attr	CG_EXT
MPI_Comm_set_errhandler	CG_ERR
MPI_Comm_set_name	CG_EXT
MPI_Comm_size	CG
MPI_Comm_spawn	SPAWN
MPI_Comm_spawn_multiple	SPAWN
MPI_Comm_split	CG
MPI_Comm_test_inter	CG
MPI_Dims_create	TOPO
MPI_Dist_graph_create	TOPO
MPI_Dist_graph_create_adjacent	TOPO
MPI_Dist_graph_neighbors	TOPO
MPI_Dist_graph_neighbors_count	TOPO
MPI_Errhandler_create	ERR
MPI_Errhandler_free	ERR
MPI_Errhandler_get	ERR
MPI_Errhandler_set	ERR
MPI_Error_class	ERR
MPI_Error_string	ERR
MPI_Exscan	COLL
MPI_File_c2f	IO_MISC
MPI_File_call_errhandler	IO_ERR
MPI_File_close	IO
MPI_File_create_errhandler	IO_ERR
MPI_File_delete	IO
MPI_File_f2c	IO_MISC
MPI_File_get_amode	IO
MPI_File_get_atomicity	IO
MPI_File_get_byte_offset	IO
MPI_File_get_errhandler	IO_ERR
MPI_File_get_group	IO
MPI_File_get_info	IO
MPI_File_get_position	IO
MPI_File_get_position_shared	IO

APPENDIX B. MPI WRAPPER AFFILIATION

MPI_File_get_size	IO
MPI_File_get_type_extent	IO
MPI_File_get_view	IO
MPI_File_iread	IO
MPI_File_iread_at	IO
MPI_File_iread_shared	IO
MPI_File_iwrite	IO
MPI_File_iwrite_at	IO
MPI_File_iwrite_shared	IO
MPI_File_open	IO
MPI_File_preallocate	IO
MPI_File_read	IO
MPI_File_read_all	IO
MPI_File_read_all_begin	IO
MPI_File_read_all_end	IO
MPI_File_read_at	IO
MPI_File_read_at_all	IO
MPI_File_read_at_all_begin	IO
MPI_File_read_at_all_end	IO
MPI_File_read_ordered	IO
MPI_File_read_ordered_begin	IO
MPI_File_read_ordered_end	IO
MPI_File_read_shared	IO
MPI_File_seek	IO
MPI_File_seek_shared	IO
MPI_File_set_atomicity	IO
MPI_File_set_errhandler	IO_ERR
MPI_File_set_info	IO
MPI_File_set_size	IO
MPI_File_set_view	IO
MPI_File_sync	IO
MPI_File_write	IO
MPI_File_write_all	IO
MPI_File_write_all_begin	IO
MPI_File_write_all_end	IO
MPI_File_write_at	IO
MPI_File_write_at_all	IO
MPI_File_write_at_all_begin	IO
MPI_File_write_at_all_end	IO

B.1 Function to group

MPI_File_write_ordered	IO
MPI_File_write_ordered_begin	IO
MPI_File_write_ordered_end	IO
MPI_File_write_shared	IO
MPI_Finalize	ENV
MPI_Finalized	ENV
MPI_Free_mem	MISC
MPI_Gather	COLL
MPI_Gatherv	COLL
MPI_Get	RMA
MPI_Get_address	MISC
MPI_Get_count	EXT
MPI_Get_elements	EXT
MPI_Get_processor_name	EXT
MPI_Get_version	MISC
MPI_Graph_create	TOPO
MPI_Graph_get	TOPO
MPI_Graph_map	TOPO
MPI_Graph_neighbors	TOPO
MPI_Graph_neighbors_count	TOPO
MPI_Graphdims_get	TOPO
MPI_Grequest_complete	EXT
MPI_Grequest_start	EXT
MPI_Group_c2f	CG_MISC
MPI_Group_compare	CG
MPI_Group_difference	CG
MPI_Group_excl	CG
MPI_Group_f2c	CG_MISC
MPI_Group_free	CG
MPI_Group_incl	CG
MPI_Group_intersection	CG
MPI_Group_range_excl	CG
MPI_Group_range_incl	CG
MPI_Group_rank	CG
MPI_Group_size	CG
MPI_Group_translate_ranks	CG
MPI_Group_union	CG
MPI_Ibsend	P2P
MPI_Info_c2f	MISC

APPENDIX B. MPI WRAPPER AFFILIATION

MPI_Info_create	MISC
MPI_Info_delete	MISC
MPI_Info_dup	MISC
MPI_Info_f2c	MISC
MPI_Info_free	MISC
MPI_Info_get	MISC
MPI_Info_get_nkeys	MISC
MPI_Info_get_nthkey	MISC
MPI_Info_get_valuelen	MISC
MPI_Info_set	MISC
MPI_Init	ENV
MPI_Init_thread	ENV
MPI_Initialized	ENV
MPI_Intercomm_create	CG
MPI_Intercomm_merge	CG
MPI_Iprobe	P2P
MPI_Irecv	P2P
MPI_Irsend	P2P
MPI_Is_thread_main	ENV
MPI_Isend	P2P
MPI_Issend	P2P
MPI_Keyval_create	CG_EXT
MPI_Keyval_free	CG_EXT
MPI_Lookup_name	SPAWN
MPI_Op_c2f	MISC
MPI_Op_commutative	MISC
MPI_Op_create	MISC
MPI_Op_f2c	MISC
MPI_Op_free	MISC
MPI_Open_port	SPAWN
MPI_Pack	TYPE
MPI_Pack_external	TYPE
MPI_Pack_external_size	TYPE
MPI_Pack_size	TYPE
MPI_Pcontrol	PERF
MPI_Probe	P2P
MPI_Publish_name	SPAWN
MPI_Put	RMA
MPI_Query_thread	ENV

B.1 Function to group

MPI_Recv	P2P
MPI_Recv_init	P2P
MPI_Reduce	COLL
MPI_Reduce_local	COLL
MPI_Reduce_scatter	COLL
MPI_Reduce_scatter_block	COLL
MPI_Register_datarep	IO
MPI_Request_c2f	MISC
MPI_Request_f2c	MISC
MPI_Request_free	P2P
MPI_Request_get_status	MISC
MPI_Rsend	P2P
MPI_Rsend_init	P2P
MPI_Scan	COLL
MPI_Scatter	COLL
MPI_Scatterv	COLL
MPI_Send	P2P
MPI_Send_init	P2P
MPI_Sendrecv	P2P
MPI_Sendrecv_replace	P2P
MPI_Sizeof	TYPE
MPI_Ssend	P2P
MPI_Ssend_init	P2P
MPI_Start	P2P
MPI_Startall	P2P
MPI_Status_c2f	MISC
MPI_Status_f2c	MISC
MPI_Status_set_cancelled	EXT
MPI_Status_set_elements	EXT
MPI_Test	P2P
MPI_Test_cancelled	P2P
MPI_Testall	P2P
MPI_Testany	P2P
MPI_Testsome	P2P
MPI_Topo_test	TOPO
MPI_Type_c2f	TYPE_MISC
MPI_Type_commit	TYPE
MPI_Type_contiguous	TYPE
MPI_Type_create_darray	TYPE

APPENDIX B. MPI WRAPPER AFFILIATION

MPI_Type_create_f90_complex	TYPE
MPI_Type_create_f90_integer	TYPE
MPI_Type_create_f90_real	TYPE
MPI_Type_create_hindexed	TYPE
MPI_Type_create_hvector	TYPE
MPI_Type_create_indexed_block	TYPE
MPI_Type_create_keyval	TYPE_EXT
MPI_Type_create_resized	TYPE
MPI_Type_create_struct	TYPE
MPI_Type_create_subarray	TYPE
MPI_Type_delete_attr	TYPE_EXT
MPI_Type_dup	TYPE
MPI_Type_extent	TYPE
MPI_Type_f2c	TYPE_MISC
MPI_Type_free	TYPE
MPI_Type_free_keyval	TYPE_EXT
MPI_Type_get_attr	TYPE_EXT
MPI_Type_get_contents	TYPE
MPI_Type_get_envelope	TYPE
MPI_Type_get_extent	TYPE
MPI_Type_get_name	TYPE_EXT
MPI_Type_get_true_extent	TYPE
MPI_Type_hindexed	TYPE
MPI_Type_hvector	TYPE
MPI_Type_indexed	TYPE
MPI_Type_lb	TYPE
MPI_Type_match_size	TYPE
MPI_Type_set_attr	TYPE_EXT
MPI_Type_set_name	TYPE_EXT
MPI_Type_size	TYPE
MPI_Type_struct	TYPE
MPI_Type_ub	TYPE
MPI_Type_vector	TYPE
MPI_Unpack	TYPE
MPI_Unpack_external	TYPE
MPI_Unpublish_name	SPAWN
MPI_Wait	P2P
MPI_Waitall	P2P
MPI_Waitany	P2P

B.2 Group to function

MPI_Waitsome	P2P
MPI_Win_c2f	RMA_MISC
MPI_Win_call_errhandler	RMA_ERR
MPI_Win_complete	RMA
MPI_Win_create	RMA
MPI_Win_create_errhandler	RMA_ERR
MPI_Win_create_keyval	RMA_EXT
MPI_Win_delete_attr	RMA_EXT
MPI_Win_f2c	RMA_MISC
MPI_Win_fence	RMA
MPI_Win_free	RMA
MPI_Win_free_keyval	RMA_EXT
MPI_Win_get_attr	RMA_EXT
MPI_Win_get_errhandler	RMA_ERR
MPI_Win_get_group	RMA
MPI_Win_get_name	RMA_EXT
MPI_Win_lock	RMA
MPI_Win_post	RMA
MPI_Win_set_attr	RMA_EXT
MPI_Win_set_errhandler	RMA_ERR
MPI_Win_set_name	RMA_EXT
MPI_Win_start	RMA
MPI_Win_test	RMA
MPI_Win_unlock	RMA
MPI_Win_wait	RMA
MPI_Wtick	EXT
MPI_Wtime	EXT

B.2 Group to function

CG - Communicators and Groups
MPI_Comm_compare, MPI_Comm_create, MPI_Comm_dup, MPI_Comm_free, MPI_Comm_group, MPI_Comm_rank, MPI_Comm_remote_group, MPI_Comm_remote_size, MPI_Comm_size, MPI_Comm_split, MPI_Comm_test_inter, MPI_Group_compare, MPI_Group_difference, MPI_Group_excl, MPI_Group_free, MPI_Group_incl, MPI_Group_intersection, MPI_Group_range_excl, MPI_Group_range_incl, MPI_Group_rank, MPI_Group_size, MPI_Group_translate_ranks, MPI_Group_union, MPI_Intercomm_create, MPI_Intercomm_merge,

APPENDIX B. MPI WRAPPER AFFILIATION

CG_ERR - Error handlers for Communicators and Groups
MPI_Comm_call_errhandler, MPI_Comm_create_errhandler, MPI_Comm_get_errhandler, MPI_Comm_set_errhandler,
CG_EXT - External interfaces for Communicators and Groups
MPI_Attr_delete, MPI_Attr_get, MPI_Attr_put, MPI_Comm_create_keyval, MPI_Comm_delete_attr, MPI_Comm_free_keyval, MPI_Comm_get_attr, MPI_Comm_get_name, MPI_Comm_set_attr, MPI_Comm_set_name, MPI_Keyval_create, MPI_Keyval_free,
CG_MISC - Miscellaneous functions for Communicators and Groups
MPI_Comm_c2f, MPI_Comm_f2c, MPI_Group_c2f, MPI_Group_f2c,
COLL - Collective communication
MPI_Allgather, MPI_Allgatherv, MPI_Allreduce, MPI_Alltoall, MPI_Alltoallv, MPI_Alltoallw, MPI_Barrier, MPI_Bcast, MPI_Exscan, MPI_Gather, MPI_Gatherv, MPI_Reduce, MPI_Reduce_local, MPI_Reduce_scatter, MPI_Reduce_scatter_block, MPI_Scan, MPI_Scatter, MPI_Scatterv,
ENV - Environmental management
MPI_Finalize, MPI_Finalized, MPI_Init, MPI_Init_thread, MPI_Initialized, MPI_Is_thread_main, MPI_Query_thread,
ERR - Common error handlers
MPI_Add_error_class, MPI_Add_error_code, MPI_Add_error_string, MPI_Errhandler_create, MPI_Errhandler_free, MPI_Errhandler_get, MPI_Errhandler_set, MPI_Error_class, MPI_Error_string,

B.2 Group to function

IO - Parallel I/O

MPI_File_close, MPI_File_delete, MPI_File_get_amode,
MPI_File_get_atomicity, MPI_File_get_byte_offset, MPI_File_get_group,
MPI_File_get_info, MPI_File_get_position, MPI_File_get_position_shared,
MPI_File_get_size, MPI_File_get_type_extent, MPI_File_get_view,
MPI_File_iread, MPI_File_iread_at, MPI_File_iread_shared,
MPI_File_iwrite, MPI_File_iwrite_at, MPI_File_iwrite_shared,
MPI_File_open, MPI_File_preallocate, MPI_File_read, MPI_File_read_all,
MPI_File_read_all_begin, MPI_File_read_all_end, MPI_File_read_at,
MPI_File_read_at_all, MPI_File_read_at_all_begin,
MPI_File_read_at_all_end, MPI_File_read_ordered,
MPI_File_read_ordered_begin, MPI_File_read_ordered_end,
MPI_File_read_shared, MPI_File_seek, MPI_File_seek_shared,
MPI_File_set_atomicity, MPI_File_set_info, MPI_File_set_size,
MPI_File_set_view, MPI_File_sync, MPI_File_write, MPI_File_write_all,
MPI_File_write_all_begin, MPI_File_write_all_end, MPI_File_write_at,
MPI_File_write_at_all, MPI_File_write_at_all_begin,
MPI_File_write_at_all_end, MPI_File_write_ordered,
MPI_File_write_ordered_begin, MPI_File_write_ordered_end,
MPI_File_write_shared, MPI_Register_datarep,

APPENDIX B. MPI WRAPPER AFFILIATION

IO_ERR - Error handlers for Parallel I/O
MPI_File_call_errhandler, MPI_File_create_errhandler, MPI_File_get_errhandler, MPI_File_set_errhandler,
IO_MISC - Miscellaneous functions for Parallel I/O
MPI_File_c2f, MPI_File_f2c,
EXT - Common external interfaces
MPI_Abort, MPI_Get_count, MPI_Get_elements, MPI_Get_processor_name, MPI_Grequest_complete, MPI_Grequest_start, MPI_Status_set_cancelled, MPI_Status_set_elements, MPI_Wtick, MPI_Wtime,
MISC - Miscellaneous functions
MPI_Address, MPI_Alloc_mem, MPI_Free_mem, MPI_Get_address, MPI_Get_version, MPI_Info_c2f, MPI_Info_create, MPI_Info_delete, MPI_Info_dup, MPI_Info_f2c, MPI_Info_free, MPI_Info_get, MPI_Info_get_nkeys, MPI_Info_get_nthkey, MPI_Info_get_valuelen, MPI_Info_set, MPI_Op_c2f, MPI_Op_commutative, MPI_Op_create, MPI_Op_f2c, MPI_Op_free, MPI_Request_c2f, MPI_Request_f2c, MPI_Request_get_status, MPI_Status_c2f, MPI_Status_f2c,
P2P - Point-to-point communication
MPI_Bsend, MPI_Bsend_init, MPI_Buffer_attach, MPI_Buffer_detach, MPI_Cancel, MPI_Ibsend, MPI_Iprobe, MPI_Irecv, MPI_Irsend, MPI_Isend, MPI_Issend, MPI_Probe, MPI_Recv, MPI_Recv_init, MPI_Request_free, MPI_Rsend, MPI_Rsend_init, MPI_Send, MPI_Send_init, MPI_Sendrecv, MPI_Sendrecv_replace, MPI_Ssend, MPI_Ssend_init, MPI_Start, MPI_Startall, MPI_Test, MPI_Test_cancelled, MPI_Testall, MPI_Testany, MPI_Testsome, MPI_Wait, MPI_Waitall, MPI_Waitany, MPI_Waitsome,
PERF - Profiling Interface
MPI_Pcontrol,
RMA - One-sided communication (Remote Memory Access)
MPI_Accumulate, MPI_Get, MPI_Put, MPI_Win_complete, MPI_Win_create, MPI_Win_fence, MPI_Win_free, MPI_Win_get_group, MPI_Win_lock, MPI_Win_post, MPI_Win_start, MPI_Win_test, MPI_Win_unlock, MPI_Win_wait,
RMA_ERR - Error handlers for One-sided communication (Remote Memory Access)
MPI_Win_call_errhandler, MPI_Win_create_errhandler, MPI_Win_get_errhandler, MPI_Win_set_errhandler,
RMA_EXT - External interfaces for One-sided communication (Remote Memory Access)

B.2 Group to function

MPI_Win_create_keyval, MPI_Win_delete_attr, MPI_Win_free_keyval,
MPI_Win_get_attr, MPI_Win_get_name, MPI_Win_set_attr,
MPI_Win_set_name,

RMA_MISC - Miscellaneous functions for One-sided communication (Remote Memory Access)

MPI_Win_c2f, MPI_Win_f2c,

SPAWN - Process spawning

MPI_Close_port, MPI_Comm_accept, MPI_Comm_connect,
MPI_Comm_disconnect, MPI_Comm_get_parent, MPI_Comm_join,
MPI_Comm_spawn, MPI_Comm_spawn_multiple, MPI_Lookup_name,
MPI_Open_port, MPI_Publish_name, MPI_Unpublish_name,

TOPO - Topology (cartesian and graph) communicators

MPI_Cart_coords, MPI_Cart_create, MPI_Cart_get, MPI_Cart_map,
MPI_Cart_rank, MPI_Cart_shift, MPI_Cart_sub, MPI_Cartdim_get,
MPI_Dims_create, MPI_Dist_graph_create, MPI_Dist_graph_create_adjacent,
MPI_Dist_graph_neighbors, MPI_Dist_graph_neighbors_count,
MPI_Graph_create, MPI_Graph_get, MPI_Graph_map,
MPI_Graph_neighbors, MPI_Graph_neighbors_count, MPI_Graphdims_get,
MPI_Topo_test,

TYPE - Datatypes

MPI_Pack, MPI_Pack_external, MPI_Pack_external_size, MPI_Pack_size,
MPI_Sizeof, MPI_Type_commit, MPI_Type_contiguous,
MPI_Type_create_darray, MPI_Type_create_f90_complex,
MPI_Type_create_f90_integer, MPI_Type_create_f90_real,
MPI_Type_create_hindexed, MPI_Type_create_hvector,
MPI_Type_create_indexed_block, MPI_Type_create_resized,
MPI_Type_create_struct, MPI_Type_create_subarray, MPI_Type_dup,
MPI_Type_extent, MPI_Type_free, MPI_Type_get_contents,
MPI_Type_get_envelope, MPI_Type_get_extent, MPI_Type_get_true_extent,
MPI_Type_hindexed, MPI_Type_hvector, MPI_Type_indexed, MPI_Type_lb,
MPI_Type_match_size, MPI_Type_size, MPI_Type_struct, MPI_Type_ub,
MPI_Type_vector, MPI_Unpack, MPI_Unpack_external,

APPENDIX B. MPI WRAPPER AFFILIATION

TYPE_EXT - External interfaces for datatypes
MPI_Type_create_keyval, MPI_Type_delete_attr, MPI_Type_free_keyval, MPI_Type_get_attr, MPI_Type_get_name, MPI_Type_set_attr, MPI_Type_set_name,
TYPE_MISC - Miscellaneous functions for datatypes
MPI_Type_c2f, MPI_Type_f2c,

Appendix C

Score-P Metric Plugin Example

```
#include <scorep/SCOREP_MetricPlugins.h>

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
/* Use mutex to make ID generation thread safe */
#include <pthread.h>

/* Maximum number of metrics */
#define NUMBER_RANDOM_METRICS 5

/* Guard for metric ID generation */
static pthread_mutex_t add_metric_mutex;

/* Number of individual metrics */
static int32_t num_metrics = 0;

int32_t
init()
{
    return 0;
}

int32_t
add_counter( char * event_name )
{
    /* ID generation has to be thread save */
    int id;

    pthread_mutex_lock( &add_metric_mutex );
    id = num_metrics;
    num_metrics++;
    pthread_mutex_unlock( &add_metric_mutex );

    return id;
}
```

APPENDIX C. SCORE-P METRIC PLUGIN EXAMPLE

```
}

SCOREP_Metric_Plugin_MetricProperties*
get_event_info( char * event_name )
{
    SCOREP_Metric_Plugin_MetricProperties *return_values;
    char name_buffer[255];
    int i;

    /* If wildcard, add some random counters */
    if ( strcmp( event_name, "*" ) == 0 )
    {
        return_values = malloc( ( NUMBER_RANDOM_METRICS + 1 ) * sizeof( SCOREP_Me
tric_Plugin_MetricProperties ) );
        for ( i = 0; i < NUMBER_RANDOM_METRICS; i++ )
        {
            sprintf( name_buffer, "random strictly sync counter #%i", i );
            return_values[ i ].name          = strdup( name_buffer );
            return_values[ i ].description = NULL;
            return_values[ i ].unit         = NULL;
            return_values[ i ].mode         = SCOREP_METRIC_MODE_ABSOLUTE_LAST;
            return_values[ i ].value_type   = SCOREP_METRIC_VALUE_UINT64;
            return_values[ i ].base         = SCOREP_METRIC_BASE_DECIMAL;
            return_values[ i ].exponent     = 0;
        }
        return_values[ NUMBER_RANDOM_METRICS ].name = NULL;
    }
    else
    {
        /* If no wildcard is given create one random counter with the passed name
        */
        return_values = malloc( 2 * sizeof( SCOREP_Metric_Plugin_MetricProperties
        ) );
        sprintf( name_buffer, "random strictly sync counter #s", event_name );
        return_values[ 0 ].name          = strdup( name_buffer );
        return_values[ 0 ].description = NULL;
        return_values[ 0 ].unit         = NULL;
        return_values[ 0 ].mode         = SCOREP_METRIC_MODE_ABSOLUTE_LAST;
        return_values[ 0 ].value_type   = SCOREP_METRIC_VALUE_UINT64;
        return_values[ 0 ].base         = SCOREP_METRIC_BASE_DECIMAL;
        return_values[ 0 ].exponent     = 0;
        return_values[ 1 ].name          = NULL;
    }
    return return_values;
}

uint64_t
get_value( int32_t counterIndex )
{
    return counterIndex;
}

void fini()
{

```

```
    pthread_mutex_destroy( &add_metric_mutex );
}

SCOREP_Metric_Plugin_Info
get_info()
{
    /* Initialize info data (with zero) */
    SCOREP_Metric_Plugin_Info info;
    memset( &info, 0, sizeof( SCOREP_Metric_Plugin_Info ) );

    /* Set up */
    info.scorep_metric_plugin_version = SCOREP_METRIC_PLUGIN_VERSION;
    info.run_per                      = SCOREP_METRIC_PER_THREAD;
    info.sync                        = SCOREP_METRIC_STRICTLY_SYNC;
    info.initialize                  = init;
    info.finalize                    = fini;
    info.get_event_info              = get_event_info;
    info.add_counter                  = add_counter;
    info.get_current_value            = get_value;

    return info;
}
```

APPENDIX C. SCORE-P METRIC PLUGIN EXAMPLE

Appendix D

Score-P Tools

D.1 scorep

A call to `scorep` has the following syntax:

This is the Score-P instrumentation tool. The usage is:
`scorep <options> <original command>`

Common options are:

<code>--help, -h</code>	Show help output. Does not execute any other command.
<code>--config=<file></code>	Specifies file for the instrumentation configuration.
<code>-v, --verbose[=<value>]</code>	Specifies the verbosity level. The following levels are available: 0 = No output 1 = Executed commands are displayed (default if no value is specified) 2 = Detailed information is displayed
<code>--dry-run</code>	Only displays the executed commands. It does not execute any command.
<code>--keep-files</code>	Do not delete temporarily created files after successful instrumentation. By default, temporary files are deleted if no error occurs during instrumentation.
<code>--version</code>	Prints the Score-P version and exits.
<code>--static</code>	Enforce static linking of the Score-P libraries.
<code>--dynamic</code>	Enforce dynamic linking of the Score-P libraries.
<code>--no-as-needed</code>	Adds a GNU ld linker flag to fix undefined references when using shared Score-P libraries. This happens on systems using <code>--as-needed</code> as linker default. It will be handled transparently in future releases of Score-P.
<code>--thread=<paradigm>[:<variant>]</code>	Possible paradigms and variants are: none No thread support. omp:pomp_tpd OpenMP support using OPARI2 thread tracking It requires <code>and</code> , thus, automatically enables <code>opari</code> instrumentation.

APPENDIX D. SCORE-P TOOLS

```
omp:ancestry
    OpenMP support using thread tracking with ancestry functions in OpenMP 3.0
    It requires and, thus, automatically enables opari instrumentation.
pthread
    Pthread support using thread tracking via library wrapping
    It conflicts and, thus, automatically disables opari instrumentation.
--mpp=<paradigm>[:<variant>]
    Possible paradigms and variants are:
    none
        No multi-process support.
    mpi
        MPI support using library wrapping
    shmem
        SHMEM support using library wrapping
--mutex=<paradigm>[:<variant>]
    Possible paradigms and variants are:
    none
        serial case, no locking
    pthread
        Pthread mutex locks
    pthread:spinlock
        Pthread spinlocks
    omp
        OpenMP locks
--nocobi
    Disables cobit instrumentation.
--compiler
    Enables compiler instrumentation.
    By default, it disables cobit and pdt instrumentation.
--nocompiler
    Disables compiler instrumentation.
--nocuda
    Disables cuda instrumentation.
--online-access
    Enables online-access support. It is disabled by default
--noonline-access
    online-access Disables online-access support.
--pomp[=<paramter-list>]
    Enables pomp user instrumentation.
    You may add additional parameters that are passed to OPARI2.
    By default, it enables also preprocessing
--nopomp
    Disables pomp user instrumentation.
--opari[=<paramter-list>]
    Enables OPARI2 instrumentation of OpenMP regions.
    You may add additional parameters that are passed to OPARI2
    By default, it enables also preprocessing and
    pomp user instrumentation.
--pdt[=<paramter-list>]
    Enables pdt instrumentation.
    You may add additional parameters that are passed to pdt.
    It requires and, thus, automatically enables user instrumentation.
    It conflicts and, thus, automatically disables preprocess instrumentation.
    By default, it disables cobit and compiler instrumentation.
--nopdt
    Disables pdt instrumentation.
--preprocess
    Enables preprocess instrumentation.
    It requires and, thus, automatically enables opari instrumentation.
    It conflicts and, thus, automatically disables pdt instrumentation.
--nopreprocess
    Disables preprocess instrumentation.
--user
    Enables user instrumentation.
--nouser
    Disables user instrumentation.
```

D.2 scorep-config

D.2 scorep-config

A call to scorep-config has the following syntax:

Usage:

```
scorep-config <command> [<options>]
```

Commands:

```
--cflags      prints additional compiler flags for a C compiler. They already
               contain the include flags.
--cxxflags    prints additional compiler flags for a C++ compiler. They already
               contain the include flags.
--fflags      prints additional compiler flags for a Fortran compiler. They already
               contain the include flags.
--cppflags    prints the include flags. They are already contained in the
               output of the --cflags, --cxxflags, and --fflags commands
--ldflags     prints the library path flags for the linker
--libs        prints the required linker flags
--cc          prints the C compiler name
--cxx         prints the C++ compiler name
--fc          prints the Fortran compiler name
--mpicc       prints the MPI C compiler name
--mpicxx      prints the MPI C++ compiler name
--mpifc       prints the MPI Fortran compiler name
--cobi-deps   prints the dependency library part for the Cobi adapter file
--help        prints this usage information
--version     prints the version number of the Score-P package
--scorep-revision prints the revision number of the Score-P package
--common-revision prints the revision number of the common package
--remap-specfile prints the path to the remapper specification file
```

Options:

```
--nvcc        Convert flags to be suitable for the nvcc compiler.
--static       Use only static Score-P libraries if possible.
--dynamic      Use only dynamic Score-P libraries if possible.
--online-access|--noonline-access
               Specifies whether online access (needed by Periscope) is enabled.
               On default it is enabled.
--compiler|--nocompiler
               Specifies whether compiler instrumentation is used.
               On default compiler instrumentation is enabled.
--user|--nouser
               Specifies whether user instrumentation is used.
               On default user instrumentation is disabled.
--pomp|--nopomp
               Specifies whether pomp instrumentation is used.
               On default pomp instrumentation is disabled.
--cuda|--nocuda
               Specifies whether cuda instrumentation is used.
               On default cuda instrumentation is enabled.
--preprocess|--nopreprocess
               Specifies whether preprocess instrumentation is used.
               On default preprocess instrumentation is disabled.
--thread=<threading system>[:<variant>]
               Available threading systems are:
```

```
none This is the default.
omp:pomp_tpd
omp:ancestry
pthread
    If no variant is specified the first matching
    threading system is used.
--mutex=<locking system>[:<variant>]
    Available locking systems are:
none
omp
pthread
pthread:spinlock
pthread:wrap
    If no variant is specified the default for the respective
    threading system is used.
--mpp=<multi-process paradigm>
    Available multi-process paradigms are:
mpi This is the default.
shmem
none
```

D.3 scorep-info

A call to `scorep-info` has the following syntax:

```
Usage: scorep-info <info command> <command options>
       scorep-info --help
This is the Score-P info tool.
```

Available info commands:

```
config-vars:
    Shows the list of all measurement config variables with a short description.

Info command options:
--full          Displays a detailed description for each config variable.
--values        Displays the current values for each config variable.
                Warning: These values may be wrong, please consult the
                manual of the batch system how to pass the values
                to the measurement job.

config-summary:
    Shows the configure summary of the Score-P package.
```

D.4 scorep-score

A call to `scorep-score` has the following syntax:

D.5 scorep-backend-info

Usage: scorep-score <profile> [options]

Options:

- r Show all regions.
- h Show this help and exit.
- f <filter> Shows the result with the filter applied.
- c <num> Specifies the number of hardware counters that shall be measured. By default, this value is 0, which means that only a timestamp is measured on each event. If you plan to record hardware counters specify the number of hardware counters. Otherwise, scorep-score may underestimate the required space.

D.5 scorep-backend-info

Note

This tool is intended to run as a batch job. Please consult the manual of the batch system how to submit jobs.

A call to scorep-backend-info has the following syntax:

Usage: scorep-backend-info <info command> <command options>
scorep-backend-info --help

This is the Score-P backend info tool.

Available info commands:

system-tree:
Shows the available system tree levels, starting with the root.

config-vars:
Shows the current values of all measurement config variables.

Appendix E

Score-P Measurement Configuration Variables

This is the list of configure variables to control a Score-P measurement.

SCOREP_ENABLE_PROFILING Enable profiling

Type: Boolean

Default: true

SCOREP_ENABLE_TRACING Enable tracing

Type: Boolean

Default: false

SCOREP_VERBOSE Be verbose

Type: Boolean

Default: false

SCOREP_TOTAL_MEMORY Total memory in bytes for the measurement system

Type: Number with size suffixes

Default: 16000k

SCOREP_PAGE_SIZE Memory page size in bytes

Type: Number with size suffixes

Default: 8k

APPENDIX E. SCORE-P MEASUREMENT CONFIGURATION VARIABLES

TOTAL_MEMORY will be split up into pages of size PAGE_SIZE.

SCOREP_EXPERIMENT_DIRECTORY Name of the experiment directory

Type: String

Default:

When no experiment name is given (the default) Score-P names the experiment directory 'scorep-measurement-tmp' and renames this after a successful measurement to a generated name based on the current time.

SCOREP_OVERWRITE_EXPERIMENT_DIRECTORY Overwrite an existing experiment directory

Type: Boolean

Default: true

If you specified a specific experiment directory name, but this name is already given, you can force overwriting it with this flag.

The previous experiment directory will be renamed.

SCOREP_MACHINE_NAME The machine name used in profile and trace output.

Type: String

Default: Linux

We suggest using a unique name, e.g., the fully qualified domain name. The default machine name was set at configure time (see the INSTALL file for customization options).

SCOREP_EXECUTABLE Executable of the application

Type: String

Default:

File name, preferably with full path, of the application's executable. It is used for evaluating the symbol table of the application, which is required by some compiler adapters.

SCOREP_PROFILING_TASK_TABLE_SIZE Size of the task tracing table

Type: Number

Default: 64

Size of the task tracing table. Best performance is obtained, if the table size matches the number of tasks that are active at once. If your program does not use tasks, you may set this value to zero, to save some memory.

SCOREP_PROFILING_MAX_CALLPATH_DEPTH Maximum depth of the call-tree

Type: Number

Default: 30

SCOREP_PROFILING_BASE_NAME Base for construction of the profile filename

Type: String

Default: profile

String which is used as based to create the filenames for the profile files.

SCOREP_PROFILING_FORMAT Profile output format

Type: Set

Default: default

Sets the output format for the profile.

The following formats are supported:

none: No profile output. This does not disable profile recording.

tau_snapshot: Tau snapshot format

cube4: Stores the sum for every metric per callpath in Cube4 format.

cube_tuple: Stores an extended set of statistics in Cube4 format.

default: Default format. If Cube4 is supported, Cube4 is the default

else the Tau snapshot format is default

SCOREP_PROFILING_ENABLE_CLUSTERING Enable clustering

Type: Boolean

Default: true

SCOREP_PROFILING_CLUSTER_COUNT maximum cluster count for iteration clustering.

APPENDIX E. SCORE-P MEASUREMENT CONFIGURATION VARIABLES

Type: Number with size suffixes

Default: 64

maximum cluster count for iteration clustering.

SCOREP_PROFILING_CLUSTERING_MODE Specifies the level of strictness when comparing call trees for equivalence.

Type: Number with size suffixes

Default: 1

Specifies the level of strictness when comparing call trees for equivalence.

SCOREP_PROFILING_CLUSTERED_REGION Name of the clustered region

Type: String

Default:

The clustering can only cluster one dynamic region. If more than one dynamic region are defined by the user, the region is clustered which is exited first. If another region should be clustered instead you can specify the region name in this variable. If the variable is unset or empty, the first exited dynamic region is clustered.

SCOREP_PROFILING_ENABLE_CORE_FILES Write .core files if an error occurred.

Type: Boolean

Default: false

If an error occurs inside the profiling system, the profiling is disabled. For debugging reasons, it might be feasible to get the state of the local local at these points. It is not recommended to enable this feature for large scale measurements.

SCOREP_TRACING_USE_SION Whether or not to use libsion as OTF2 substrate

Type: Boolean

Default: false

SCOREP_TRACING_MAX_PROCS_PER_SION_FILE Maximum number of processes that share one sion file (must be > 0)

Type: Number

Default: 1024

All processes are than evenly distributed over the number of needed files to fulfill this constraint. E.g., having 4 processes and setting the maximum to 3 would result in 2 files each holding 2 processes.

SCOREP_TRACING_COMPRESS Whether or not to compress traces with libz

Type: Boolean

Default: false

SCOREP_ONLINEACCESS_ENABLE Enable online access interface

Type: Boolean

Default: false

SCOREP_ONLINEACCESS_REG_PORT Online access registry service port

Type: Number

Default: 50100

SCOREP_ONLINEACCESS_REG_HOST Online access registry service hostname

Type: String

Default: localhost

SCOREP_ONLINEACCESS_BASE_PORT Base port for online access server

Type: Number

Default: 50010

SCOREP_ONLINEACCESS_APPL_NAME Application name to be registered

Type: String

Default: appl

SCOREP_FILTERING_FILE A file name which contain the filter rules

Type: String

Default:

SCOREP_METRIC_PAPI PAPI metric names to measure

Type: String

APPENDIX E. SCORE-P MEASUREMENT CONFIGURATION VARIABLES

Default:

List of requested metric names that will be collected during program run.

SCOREP_METRIC_PAPI_PER_PROCESS PAPI metric names to measure per-process

Type: String

Default:

List of requested metric names that will be recorded only by first thread of a process.

SCOREP_METRIC_PAPI_SEP Separator of metric names

Type: String

Default: ,

Character that separates metric names in SCOREP_METRIC_PAPI and SCOREP_METRIC_PAPI_PER_PROCESS.

SCOREP_METRIC_RUSAGE Resource usage metric names to measure

Type: String

Default:

List of requested resource usage metric names that will be collected during program run.

SCOREP_METRIC_RUSAGE_PER_PROCESS Resource usage metric names to measure per-process

Type: String

Default:

List of requested resource usage metric names that will be recorded only by first thread of a process.

SCOREP_METRIC_RUSAGE_SEP Separator of resource usage metric names.

Type: String

Default: ,

Character that separates metric names in SCOREP_METRIC_RUSAGE and SCOREP_METRIC_RUSAGE_PER_PROCESS.

SCOREP_METRIC_PLUGINS Specify list of used plugins

Type: String

Default:

List of requested metric plugin names that will be used during program run.

SCOREP_METRIC_PLUGINS_SEP Separator of plugin names

Type: String

Default: ,

Character that separates plugin names in SCOREP_METRIC_PLUGINS.

SCOREP_SELECTIVE_CONFIG_FILE A file name which configures selective recording

Type: String

Default:

SCOREP_MPI_MAX_COMMUNICATORS Determines the number of concurrently used communicators per process

Type: Number

Default: 50

SCOREP_MPI_MAX_WINDOWS Determines the number of concurrently used windows for MPI one-sided communication per process

Type: Number

Default: 50

SCOREP_MPI_MAX_ACCESS_EPOCHS Maximum amount of concurrently active access or exposure epochs per process

Type: Number

Default: 50

SCOREP_MPI_MAX_GROUPS Maximum number of concurrently used MPI groups per process

Type: Number

Default: 50

APPENDIX E. SCORE-P MEASUREMENT CONFIGURATION VARIABLES

SCOREP_MPI_ENABLE_GROUPS The names of the function groups which are measured

Type: Set

Default: default

Other functions are not measured.

Possible groups are:

all: All MPI functions

cg: Communicator and group management

coll: Collective functions

default: Default configuration

env: Environmental management

err: MPI Error handling

ext: External interface functions

io: MPI file I/O

misc: Miscellaneous

perf: PControl

p2p: Peer-to-peer communication

rma: One sided communication

spawn: Process management

topo: Topology

type: MPI datatype functions

xnonblock: Extended non-blocking events

xrequest: Test events for uncompleted requests

SCOREP_MPI_ONLINE_ANALYSIS Enable online mpi wait states analysis

Type: Boolean

Default: false

SCOREP_CUDA_ENABLE CUDA measurement features

Type: Set

Default: no

Sets the CUDA measurement mode to capture:

runtime: CUDA runtime API

driver: CUDA driver API

kernel: CUDA kernels

kernel_serial: Serialized kernel recording.

kernel_counter: Fixed CUDA kernel metrics.

idle: GPU compute idle time

pure_idle: GPU idle time (memory copies are not idle)

memcpy: CUDA memory copies

sync: Record implicit and explicit CUDA synchronization

gpumemusage: Record CUDA memory (de)allocations as a counter

references: Record references between CUDA activities

flushatexit: Flush CUDA activity buffer at program exit

default/yes/1: CUDA runtime API and GPU activities

no: Disable CUDA measurement

SCOREP_CUDA_BUFFER Total memory in bytes for the CUDA record buffer

Type: Number with size suffixes

Default: 1M

SCOREP_CUDA_BUFFER_CHUNK Chunk size in bytes for the CUDA record buffer (ignored for CUDA 5.5 and earlier)

Type: Number with size suffixes

Default: 8k

**APPENDIX E. SCORE-P MEASUREMENT CONFIGURATION
VARIABLES**

Appendix F

Module Documentation

F.1 Score-P User Adapter

Files

- file [SCOREP_User.h](#)

This file contains the interface for the manual user instrumentation.

- file [SCOREP_User_Types.h](#)

This file contains type definitions for manual user instrumentation.

Macros for region instrumentation

- `#define SCOREP_USER_OA_PHASE_BEGIN(handle, name, type)`
- `#define SCOREP_USER_OA_PHASE_END(handle) SCOREP_User_OaPhaseEnd(handle);`
- `#define SCOREP_USER_REGION_BEGIN(handle, name, type)`
- `#define SCOREP_USER_REGION_INIT(handle, name, type)`
- `#define SCOREP_USER_REGION_END(handle) SCOREP_User_RegionEnd(handle);`
- `#define SCOREP_USER_REGION_ENTER(handle) SCOREP_User_RegionEnter(handle);`
- `#define SCOREP_USER_REGION_DEFINE(handle) static SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;`
- `#define SCOREP_USER_FUNC_DEFINE()`
- `#define SCOREP_USER_FUNC_BEGIN()`
- `#define SCOREP_USER_FUNC_END() SCOREP_User_RegionEnd(scorep_user_func_handle);`

APPENDIX F. MODULE DOCUMENTATION

- #define SCOREP_USER_GLOBAL_REGION_DEFINE(handle) SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;
- #define SCOREP_USER_GLOBAL_REGION_EXTERNAL(handle) extern SCOREP_User_RegionHandle handle;

Macros for parameter instrumentation

- #define SCOREP_USER_PARAMETER_INT64(name, value)
- #define SCOREP_USER_PARAMETER_UINT64(name, value)
- #define SCOREP_USER_PARAMETER_STRING(name, value)

Macros to provide user metrics

- #define SCOREP_USER_METRIC_LOCAL(metricHandle)
- #define SCOREP_USER_METRIC_GLOBAL(metricHandle)
- #define SCOREP_USER_METRIC_EXTERNAL(metricHandle) extern SCOREP_SamplingSetHandle metricHandle;
- #define SCOREP_USER_METRIC_INIT(metricHandle, name, unit, type, context) SCOREP_User_InitMetric(&metricHandle, name, unit, type, context);
- #define SCOREP_USER_METRIC_INT64(metricHandle, value)
- #define SCOREP_USER_METRIC_UINT64(metricHandle, value)
- #define SCOREP_USER_METRIC_DOUBLE(metricHandle, value)

C++ specific macros for region instrumentation

- #define SCOREP_USER_REGION(name, type)

Macros for measurement control

- #define SCOREP_RECORDING_ON() SCOREP_User_EnableRecording();
- #define SCOREP_RECORDING_OFF() SCOREP_User_DisableRecording();
- #define SCOREP_RECORDING_IS_ON() SCOREP_User_RecordingEnabled()

Region types

- #define SCOREP_USER_REGION_TYPE_COMMON 0
- #define SCOREP_USER_REGION_TYPE_FUNCTION 1
- #define SCOREP_USER_REGION_TYPE_LOOP 2
- #define SCOREP_USER_REGION_TYPE_DYNAMIC 4
- #define SCOREP_USER_REGION_TYPE_PHASE 8

F.1 Score-P User Adapter

Metric types

- `#define SCOREP_USER_METRIC_TYPE_INT64 0`
- `#define SCOREP_USER_METRIC_TYPE_UINT64 1`
- `#define SCOREP_USER_METRIC_TYPE_DOUBLE 2`

Metric contexts

- `#define SCOREP_USER_METRIC_CONTEXT_GLOBAL 0`
- `#define SCOREP_USER_METRIC_CONTEXT_CALLPATH 1`

F.1.1 Detailed Description

The user adapter provides a set of macros for user manual instrumentation. The macros are inserted in the source code and call functions of the Score-P runtime system. The user should avoid calling the Score-P runtime functions directly.

For every macro, two definitions are provided: The first one inserts calls to the Score-P runtime system, the second definitions resolve to nothing. Which implementation is used, depends on the definition of `SCOREP_USER_ENABLE`. If `SCOREP_USER_ENABLE` is defined, the macros resolve to calls to the Score-P runtime system. If `SCOREP_USER_ENABLE` is undefined, the user instrumentation is removed by the preprocessor. This flag `SCOREP_USER_ENABLE` should be set through the instrumentation wrapper tool automatically if user manual instrumentation is enabled.

Every source file which is instrumented must include a header file with the Score-P user instrumentation header. For C/C++ programs, the header file is 'scorep/SCOREP_User.h', for Fortran files, 'scorep/SCOREP_User.inc' must be included. Because the Fortran compilers cannot expand macros, the Fortran source code must be preprocessed by a C or C++ preprocessor, to include the headers and expand the macros. Which Fortran files are passed to the preprocessor depends on the suffix. Usually, suffixes .f and .f90 are not preprocessed, .F and .F90 files are preprocessed. However, this may depend on the used compiler.

F.1.2 Define Documentation

F.1.2.1 `#define SCOREP_RECORDING_IS_ON() SCOREP_User.RecordingEnabled()`

In C/C++ it behaves like a function call which returns whether recording is enabled or not. It returns false if the recording of events is disabled, else it returns true.

C/C++ example:

```
void foo()
{
    if ( SCOREP_RECORDING_IS_ON() )
    {
        // do something
    }
}
```

In Fortran, this macro has a different syntax. An integer variable must be specified as parameter, which is set to non-zero if recording is enabled, else the value is set to zero.

Fortran example:

```
subroutine foo
    integer :: l

    SCOREP_RECORDING_IS_ON( l )
    if (l .eq. 0) then
        ! do something
    end if

end subroutine foo
```

F.1.2.2 **#define SCOREP_RECORDING_OFF() SCOREP_User.DisableRecording();**

Disables recording of events. If already disabled, this command has no effect. The control is not restricted to events from the user adapter, but disables the recording of all events.

C/C++ example:

```
void foo()
{
    SCOREP_RECORDING_OFF()

    // do something

    SCOREP_RECORDING_ON()
}
```

Fortran example:

```
subroutine foo

    SCOREP_RECORDING_OFF()
    ! do something
    SCOREP_RECORDING_ON()

end subroutine foo
```

F.1 Score-P User Adapter

F.1.2.3 `#define SCOREP_RECORDING_ON() SCOREP_User_EnableRecording();`

Enables recording of events. If already enabled, this command has no effect. The control is not restricted to events from the user adapter, but enables the recording of all events.

C/C++ example:

```
void foo()
{
    SCOREP_RECORDING_OFF()

    // do something

    SCOREP_RECORDING_ON()
}
```

Fortran example:

```
subroutine foo

    SCOREP_RECORDING_OFF()
! do something
    SCOREP_RECORDING_ON()

end subroutine foo
```

F.1.2.4 `#define SCOREP_USER_FUNC_BEGIN()`

Value:

```
static SCOREP_User_RegionHandle \
    scorep_user_func_handle = SCOREP_USER_INVALID_REGION; \
SCOREP_User_RegionBegin( &scorep_user_func_handle, &SCOREP_User_LastFileName, \
    \
    &SCOREP_User_LastFileHandle, SCOREP_USER_FUNCTION_NAME, \
    ME, \
    SCOREP_USER_REGION_TYPE_FUNCTION, __FILE__, __LINE__ \
    );
```

This macro marks the start of a function. It should be inserted at the beginning of the instrumented function. It will generate a region, with the function name.

The C/C++ version of this command takes no arguments. It contains a variable declaration and a function call. Compilers that require a strict separation between declaration block and execution block may fail if this macro is used.

In Fortran one argument is required for the name of the function. Furthermore, the handle must be declared explicitly in Fortran.

Parameters

<i>name</i>	Fortran only: A string containing the name of the function.
-------------	-------------------------------------------------------------

C/C++ example:

```
void myfunc()
{
    // declarations

    SCOREP_USER_FUNC_BEGIN()

    // do something

    SCOREP_USER_FUNC_END()
}
```

Fortran example:

```
subroutine myfunc
    SCOREP_USER_FUNC_DEFINE()
    ! more declarations

    SCOREP_USER_FUNC_BEGIN( "myfunc" )
    ! do something
    SCOREP_USER_FUNC_END()

end subroutine myfunc
```

Note that in Fortran the function need to be declared using SCOREP_USER_FUNC_DEFINE before.

F.1.2.5 #define SCOREP_USER_FUNC_DEFINE()

This macro is for Fortran only. It declares the handle for a function. Every function handle must be declared in the declaration part of the subroutine or function if the SCOREP_USER_FUNC_BEGIN and SCOREP_USER_FUNC_END macros are used.

Example:

```
subroutine myfunc
    SCOREP_USER_FUNC_DEFINE()
    ! more declarations

    SCOREP_USER_FUNC_BEGIN( "myfunc" )
    ! do something
    SCOREP_USER_FUNC_END()

end subroutine myfunc
```

F.1 Score-P User Adapter

Note that in Fortran the function need to be declared using SCOREP_USER_FUNC_DEFINE before.

F.1.2.6 #define SCOREP_USER_FUNC_END() SCOREP_User_RegionEnd(scorep_user_func_handle);

This macro marks the end of a function. It should be inserted at every return point of the instrumented function.

C/C++ example:

```
void myfunc()
{
    // declarations

    SCOREP_USER_FUNC_BEGIN()

    // do something
    if ( some_expression )
    {
        SCOREP_USER_FUNC_END()
        return;
    }

    SCOREP_USER_FUNC_END()
}
```

Fortran example:

```
subroutine myfunc
    SCOREP_USER_FUNC_DEFINE()
    ! more declarations

    SCOREP_USER_FUNC_BEGIN( "myfunc" )
    ! do something
    SCOREP_USER_FUNC_END()

end subroutine myfunc
```

Note that in Fortran the function need to be declared using SCOREP_USER_FUNC_DEFINE before.

F.1.2.7 #define SCOREP_USER_GLOBAL_REGION_DEFINE(handle) SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;

This macro defines a region handle in a global scope for usage in more than one code block. If a region is used in multiple source files, only one of them must contain the definition using SCOREP_USER_GLOBAL_REGION_DEFINE. All

other files, in which the global handle is accessed, must only declare the global handle with `SCOREP_USER_GLOBAL_REGION_EXTERNAL(handle)`. It is possible to use the global handle in more than one code-block. However, code-blocks that share a handle, are handled as they were all the same region. Enter and exit events for global regions are created with `SCOREP_USER_REGION_BEGIN` and `SCOREP_USER_REGION_END`, respectively. Its name and type is determined at the first enter event and is not changed on later events, even if other code blocks contain a different name or type in their `SCOREP_USER_REGION_BEGIN` statement.

This macro is not available in Fortran.

Parameters

<i>handle</i>	A unique name for the handle must be provided. This handle is declared in the macro. This handle is used in the <code>SCOREP_USER_REGION_BEGIN</code> and <code>SCOREP_USER_REGION_END</code> statements to specify which region is started, or ended. If you are using a Fortran version which has a limited length of code lines, the length of the <i>handle</i> parameter must be at most 4 characters, else the declaration line exceeds the allowed length.
---------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

C/C++ example:

```
// In File1:
SCOREP_USER_GLOBAL_REGION_DEFINE( my_global_handle )

void myfunc()
{
    SCOREP_USER_REGION_BEGIN( my_global_handle, "my_global",
        SCOREP_USER_REGION_TYPE_PHASE )

    // do something

    SCOREP_USER_REGION_END( my_global_handle )
}

// In File2:
SCOREP_USER_GLOBAL_REGION_EXTERNAL( my_global_handle )

void foo()
{
    SCOREP_USER_REGION_BEGIN( my_global_handle, "my_global",
        SCOREP_USER_REGION_TYPE_PHASE )

    // do something

    SCOREP_USER_REGION_END( my_global_handle )
}
```


F.1 Score-P User Adapter

F.1.2.8 `#define SCOREP_USER_GLOBAL_REGION_EXTERNAL(handle) extern SCOREP_User_RegionHandle handle;`

This macro declares an externally defined global region. If a region is used in multiple source files, only one of them must contain the definition using `SCOREP_USER_GLOBAL_REGION_DEFINE`. All other files, in which the global handle is accessed, must only declare the global handle with `SCOREP_USER_GLOBAL_REGION_EXTERNAL(handle)`. It is possible to use the global handle in more than one code-block. However, code-blocks that share a handle, are handled as they were all the same region. Enter and exit events for global regions are created with `SCOREP_USER_REGION_BEGIN` and `SCOREP_USER_REGION_END`, respectively. Its name and type is determined at the first enter event and is not changed on later events, even if other code blocks contain a different name or type in their `SCOREP_USER_REGION_BEGIN` statement.

This macro is not available in Fortran

Parameters

<i>handle</i>	A name for a variable must be provided. This variable name must be the same like for the corresponding <code>SCOREP_USER_GLOBAL_REGION_DEFINE</code> statement. The handle is used in the <code>SCOREP_USER_REGION_BEGIN</code> and <code>SCOREP_USER_REGION_END</code> statements to specify which region is started, or ended.
---------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

C/C++ example:

```
// In File 1
SCOREP_USER_GLOBAL_REGION_DEFINE( my_global_handle )

void myfunc()
{
    SCOREP_USER_REGION_BEGIN( my_global_handle, "my_global",
        SCOREP_USER_REGION_TYPE_PHASE )

    // do something

    SCOREP_USER_REGION_END( my_global_handle )
}

// In File 2
SCOREP_USER_GLOBAL_REGION_EXTERNAL( my_global_handle )

void foo()
{
    SCOREP_USER_REGION_BEGIN( my_global_handle, "my_global",
        SCOREP_USER_REGION_TYPE_PHASE )

    // do something
```

APPENDIX F. MODULE DOCUMENTATION

```
SCOREP_USER_REGION_END( my_global_handle )
}
```

F.1.2.9 **#define SCOREP_USER_METRIC_CONTEXT_CALLPATH 1**

Indicates that a user counter is is measured for every callpath.

F.1.2.10 **#define SCOREP_USER_METRIC_CONTEXT_GLOBAL 0**

Indicates that a user counter is is measured for the global context.

F.1.2.11 **#define SCOREP_USER_METRIC_DOUBLE(*metricHandle*, *value*)**

Value:

```
SCOREP_User_TriggerMetricDouble( \
    metricHandle, value );
```

Triggers a new event for a user counter of a double precision floating point data type. Each user metric must be declared with `SCOREP_USER_COUNTER_LOCAL`, `SCOREP_USER_COUNTER_GLOBAL`, or `SCOREP_USER_COUNTER_EXTERNAL` and initialized with `SCOREP_USER_COUNTER_INIT` before it is triggered for the first time.

Parameters

<i>metricHandle</i>	The handle of the metric for which avalue is given in this statement.
<i>value</i>	The value of the counter. It must be possible for implicit casts to cast it to a double.

Example:

```
SCOREP_USER_METRIC_LOCAL( my_local_metric )

int main()
{
    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", \
        SCOREP_USER_METRIC_TYPE_DOUBLE, \
        SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
}

void foo()
```

F.1 Score-P User Adapter

```
{
    double my_double = get_some_double_value();
    SCOREP_USER_METRIC_DOUBLE( my_local_metric, my_double )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_METRIC_LOCAL( my_local_metric )
    real (kind=selected_int_kind(14,200)):: my_real = 24.5
    ! more declarations

    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", &
                             SCOREP_USER_METRIC_TYPE_DOUBLE, &
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    ! do something

    SCOREP_USER_METRIC_DOUBLE( my_local_metric, my_real )
end program myProg
```

F.1.2.12 #define SCOREP_USER_METRIC_EXTERNAL(*metricHandle*) extern SCOREP_SamplingSetHandle metricHandle;

Declares an externally defined handle for a user metric. Every global metric must be declared only in one file using SCOREP_USER_METRIC_GLOBAL. All other files in which this handle is accessed must declare it with SCOREP_USER_METRIC_EXTERNAL.

This macro is not available in Fortran.

Parameters

<i>metricHandle</i>	The variable name of the handle. it must be the same name as used in the corresponding SCOREP_USER_METRIC_GLOBAL statement.
---------------------	-----------------------------------------------------------------------------------------------------------------------------

C/C++ example:

```
// In File 1
SCOREP_USER_METRIC_GLOBAL( my_global_metric )

int main()
{
    SCOREP_USER_METRIC_INIT( my_global_metric, "My Global Metric", "seconds", \
                             SCOREP_USER_METRIC_TYPE_UINT64, \
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
```

APPENDIX F. MODULE DOCUMENTATION

```
}

void foo()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_global_metric, my_int )
}

// In File 2
SCOREP_USER_METRIC_EXTERNAL( my_global_metric )

void bar()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_global_metric, my_int )
}
```

F.1.2.13 #define SCOREP_USER_METRIC_GLOBAL(*metricHandle*)

Value:

```
SCOREP_SamplingSetHandle metricHandle \
    = SCOREP_INVALID_SAMPLING_SET;
```

Declares a handle for a user metric as a global variable. It must be used if a metric handle is accessed in more than one file. Every global metric must be declared only in one file using SCOREP_USER_METRIC_GLOBAL. All other files in which this handle is accessed must declare it with SCOREP_USER_METRIC_EXTERNAL.

This macro is not available in Fortran.

Parameters

<i>metricHandle</i>	The variable name for the handle. If you are using a Fortran version which has a limited length of code lines, the length of the <i>handle</i> parameter must be at most 4 characters, else the declaration line exceeds the allowed length.
---------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

C/C++ example:

```
// In File 1
SCOREP_USER_METRIC_GLOBAL( my_global_metric )

int main()
{
    SCOREP_USER_METRIC_INIT( my_global_metric, "My Global Metric", "seconds", \
```

F.1 Score-P User Adapter

```
SCOREP_USER_METRIC_TYPE_UINT64, \
SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
}

void foo()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_global_metric, my_int )
}

// In File 2
SCOREP_USER_METRIC_EXTERNAL( my_global_metric )

void bar()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_global_metric, my_int )
}
```

F.1.2.14 #define SCOREP_USER_METRIC_INIT(*metricHandle*, *name*, *unit*, *type*, *context*) SCOREP_User_InitMetric(&metricHandle, name, unit, type, context);

Initializes a new user counter. Each counter must be initialized before it is triggered the first time. The handle must be declared using SCOREP_USER_METRIC_LOCAL, SCOREP_USER_METRIC_GLOBAL, or SCOREP_USER_METRIC_EXTERNAL.

Parameters

<i>metricHandle</i>	Provides a variable name of the variable to store the metric handle. The variable is declared by the macro.
<i>name</i>	A string containing a unique name for the counter.
<i>unit</i>	A string containing a the unit of the data.
<i>type</i>	Specifies the data type of the counter. It must be one of the following: SCOREP_USER_METRIC_TYPE_INT64, SCOREP_USER_METRIC_TYPE_UINT64, SCOREP_USER_METRIC_TYPE_DOUBLE. In Fortran is SCOREP_USER_METRIC_TYPE_UINT64 not available.
<i>context</i>	Specifies the context for which the counter is measured. IT must be one of the following: SCOREP_USER_METRIC_CONTEXT_GLOBAL, or SCOREP_USER_METRIC_CONTEXT_CALLPATH.

C/C++ example:

```
SCOREP_USER_METRIC_LOCAL( my_local_metric )
```

APPENDIX F. MODULE DOCUMENTATION

```
int main()
{
    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", \
                             SCOREP_USER_METRIC_TYPE_UINT64, \
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
}

void foo()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_local_metric, my_int )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_METRIC_LOCAL( my_local_metric )
    integer (kind=selected_int_kind(8)):: my_int = 19
    ! more declarations

    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", &
                             SCOREP_USER_METRIC_TYPE_INT64, &
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    ! do something

    SCOREP_USER_METRIC_INT64( my_local_metric, my_int )
end program myProg
```

F.1.2.15 #define SCOREP_USER_METRIC_INT64(*metricHandle*, *value*)

Value:

```
SCOREP_User_TriggerMetricInt64( \
    metricHandle, value );
```

Triggers a new event for a user counter of a 64 bit integer data type. Each user metric must be declared with `SCOREP_USER_COUNTER_LOCAL`, `SCOREP_USER_COUNTER_GLOBAL`, or `SCOREP_USER_COUNTER_EXTERNAL` and initialized with `SCOREP_USER_COUNTER_INIT` before it is triggered for the first time.

Parameters

<i>metricHandle</i>	The handle of the metric for which a value is given in this statement.
<i>value</i>	The value of the counter. It must be possible for implicit casts to cast it to a 64 bit integer.

F.1 Score-P User Adapter

C/C++ example:

```
SCOREP_USER_METRIC_LOCAL( my_local_metric )

int main()
{
    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", \
        SCOREP_USER_METRIC_TYPE_INT64, \
        SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
}

void foo()
{
    int64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_INT64( my_local_metric, my_int )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_METRIC_LOCAL( my_local_metric )
    integer (kind=selected_int_kind(8)):: my_int = 19
    ! more declarations

    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", &
        SCOREP_USER_METRIC_TYPE_INT64, &
        SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    ! do something

    SCOREP_USER_METRIC_INT64( my_local_metric, my_int )
end program myProg
```

F.1.2.16 #define SCOREP_USER_METRIC_LOCAL(*metricHandle*)

Value:

```
static SCOREP_SamplingSetHandle \
    metricHandle \

    = SCOREP_INVALID_SAMPLING_SET;
```

Declares a handle for a user metric. It defines a variable which must be in scope at all places where the metric is used. If it is used in more than one place it need to be a global definition.

Parameters

APPENDIX F. MODULE DOCUMENTATION

<i>metricHandle</i>	The name of the variable which will be declared for storing the metric handle.
---------------------	--------------------------------------------------------------------------------

C/C++ example:

```
SCOREP_USER_METRIC_LOCAL( my_local_metric )

int main()
{
    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", \
                             SCOREP_USER_METRIC_TYPE_UINT64, \
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    // do something
}

void foo()
{
    uint64 my_int = get_some_int_value();
    SCOREP_USER_METRIC_UINT64( my_local_metric, my_int )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_METRIC_LOCAL( my_local_metric )
    integer (kind=selected_int_kind(8)):: my_int = 19
    ! more declarations

    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", &
                             SCOREP_USER_METRIC_TYPE_INT64, &
                             SCOREP_USER_METRIC_CONTEXT_GLOBAL )

    ! do something

    SCOREP_USER_METRIC_INT64( my_local_metric, my_int )
end program myProg
```

F.1.2.17 #define SCOREP_USER_METRIC_TYPE_DOUBLE 2

Indicates that a user counter is of data type double.

F.1.2.18 #define SCOREP_USER_METRIC_TYPE_INT64 0

Indicates that a user counter is of data type signed 64 bit integer.

F.1 Score-P User Adapter

F.1.2.19 `#define SCOREP_USER_METRIC_TYPE_UINT64 1`

Indicates that a user counter is of data type unsigned 64 bit integer.

F.1.2.20 `#define SCOREP_USER_METRIC_UINT64(metricHandle, value)`

Value:

```
SCOREP_User_TriggerMetricInt64( \  
    metricHandle, value );
```

Triggers a new event for a user counter of a 64 bit unsigned integer data type. Each user metric must be declared with `SCOREP_USER_COUNTER_LOCAL`, `SCOREP_USER_COUNTER_GLOBAL`, or `SCOREP_USER_COUNTER_EXTERNAL` and initialized with `SCOREP_USER_COUNTER_INIT` before it is triggered for the first time.

In Fortran is the unsigned integer type metric not available.

Parameters

<i>metricHandle</i>	The handle of the metric for which a value is given in this statement.
<i>value</i>	The value of the counter. It must be possible for implicit casts to cast it to a 64 bit unsigned integer.

Example:

```
SCOREP_USER_METRIC_LOCAL( my_local_metric )  
  
int main()  
{  
    SCOREP_USER_METRIC_INIT( my_local_metric, "My Metric", "seconds", \  
        SCOREP_USER_METRIC_TYPE_UINT64, \  
        SCOREP_USER_METRIC_CONTEXT_GLOBAL )  
  
    // do something  
}  
  
void foo()  
{  
    uint64 my_int = get_some_int_value();  
    SCOREP_USER_METRIC_UINT64( my_local_metric, my_int )  
}
```

F.1.2.21 `#define SCOREP_USER_OA_PHASE_BEGIN(handle, name, type)`

Value:

APPENDIX F. MODULE DOCUMENTATION

```
SCOREP_User_OaPhaseBegin( \
    &handle, &SCOREP_User_LastFileName, &SCOREP_User_LastFileHandle, name, \
    type, __FILE__, __LINE__ );
```

This macro marks the start of a user defined Online Access phase region. The SCOREP_USER_OA_PHASE_BEGIN and SCOREP_USER_OA_PHASE_END must be correctly nested and be a potential global synchronization points, also it is recommended to mark the body of the application's main loop as a Online Access phase in order to utilize main loop iterations for iterative online analysis.

Parameters

<i>handle</i>	The handle of the associated user region, which will become a root of the profile call-tree. This handle must be declared using SCOREP_USER_REGION_DEFINE or SCOREP_USER_GLOBAL_REGION_DEFINE before.
<i>name</i>	A string containing the name of the new region. The name should be unique.
<i>type</i>	Specifies the type of the region. Possible values are SCOREP_USER_REGION_TYPE_COMMON, SCOREP_USER_REGION_TYPE_FUNCTION, SCOREP_USER_REGION_TYPE_LOOP, SCOREP_USER_REGION_TYPE_DYNAMIC, SCOREP_USER_REGION_TYPE_PHASE, or a combination of them.

C/C++ example:

```
void main()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // application initialization

    for ( ) // main loop of the application
    {
        SCOREP_USER_OA_PHASE_BEGIN( my_region_handle, "main loop",
        SCOREP_USER_REGION_TYPE_COMMON )

        // do something

        SCOREP_USER_OA_PHASE_END( my_region_handle )
    }

    // application finalization
}
```

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )
```

F.1 Score-P User Adapter

```
! applications initialization

! main loop of the application
do ...

SCOREP_USER_OA_PHASE_BEGIN( my_region_handle, "main loop",
SCOREP_USER_REGION_TYPE_COMMON )

! do something

SCOREP_USER_OA_PHASE_END( my_region_handle )

enddo

!application finalization

end program myProg
```

F.1.2.22 `#define SCOREP_USER_OA_PHASE_END(handle) SCOREP_User_OaPhaseEnd(
handle);`

This macro marks the end of a user defined Online Access phase region. The SCOREP_USER_OA_PHASE_BEGIN and SCOREP_USER_OA_PHASE_END must be correctly nested and be a potential global synchronization points, also it is recommended to mark the body of the application's main loop as a Online Access phase in order to utilize main loop iterations for iterative online analysis.

Parameters

APPENDIX F. MODULE DOCUMENTATION

<i>handle</i>	<p>The handle of the associated user region, which will become a root of the profile call-tree. This handle must be declared using SCOREP_USER_REGION_DEFINE or SCOREP_USER_GLOBAL_REGION_DEFINE before. C/C++ example:</p> <pre>void main() { SCOREP_USER_REGION_DEFINE(my_region_handle) // application initialization for () // main loop of the application { SCOREP_USER_OA_PHASE_BEGIN(my_region_handle, "main loop", SCOREP_USER_REGION_TYPE_COMMON) // do something SCOREP_USER_OA_PHASE_END(my_region_handle) } // application finalization }</pre>
---------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    ! applications initialization

        ! main loop of the application
        do ...

            SCOREP_USER_OA_PHASE_BEGIN( my_region_handle, "main loop",
            SCOREP_USER_REGION_TYPE_COMMON )

                ! do something

            SCOREP_USER_OA_PHASE_END( my_region_handle )

        enddo

        !application finalization

    end program myProg
```

F.1.2.23 #define SCOREP_USER_PARAMETER_INT64(name, value)

Value:

F.1 Score-P User Adapter

```
{ \
    static SCOREP_User_ParameterHandle scorep_param =
    SCOREP_USER_INVALID_PARAMETER; \
    SCOREP_User_ParameterInt64( &scorep_param, name, value ); }
```

This statement adds a 64 bit signed integer type parameter for parameter-based profiling to the current region. The call-tree for the region is split according to the different values of the parameters with the same name. It is possible to add an arbitrary number of parameters to a region. Each parameter must have a unique name. However, it is not recommended to use more than 1 parameter per region.

Parameters

<i>name</i>	A string containing the name of the parameter.
<i>value</i>	The value of the parameter. It must be possible for implicit casts to cast it to a 64 bit integer.

C/C++ example:

```
void myfunc(int64 myint)
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )
    SCOREP_USER_PARAMETER_INT64("A nice int",myint)

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

F.1.2.24 #define SCOREP_USER_PARAMETER_STRING(*name*, *value*)

Value:

```
{ \
    static SCOREP_User_ParameterHandle scorep_param =
    SCOREP_USER_INVALID_PARAMETER; \
    SCOREP_User_ParameterString( &scorep_param, name, value ); }
```

This statement adds a string type parameter for parameter-based profiling to the current region. The call-tree for the region is split according to the different values of the parameters with the same name. It is possible to add an arbitrary number of parameters to a region. Each parameter must have a unique name. However, it is not recommended to use more than 1 parameter per region. During one visit it is not allowed to use the same name twice for two different parameters.

APPENDIX F. MODULE DOCUMENTATION

Parameters

<i>name</i>	A string containing the name of the parameter.
<i>value</i>	The value of the parameter. It must be a pointer to a C-string (a NULL-terminated string).

C/C++ Example:

```
void myfunc(char *mystring)
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )
    SCOREP_USER_PARAMETER_STRING("A nice string",mystring)

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

F.1.2.25 #define SCOREP_USER_PARAMETER_UINT64(*name*, *value*)

Value:

```
{ \
    static SCOREP_User_ParameterHandle scorep_param =
    SCOREP_USER_INVALID_PARAMETER; \
    SCOREP_User_ParameterUint64( &scorep_param, name, value ); }
```

This statement adds a 64 bit unsigned integer type parameter for parameter-based profiling to the current region. The call-tree for the region is split according to the different values of the parameters with the same name. It is possible to add an arbitrary number of parameters to a region. Each parameter must have a unique name. However, it is not recommended to use more than 1 parameter per region.

Parameters

<i>name</i>	A string containing the name of the parameter.
<i>value</i>	The value of the parameter. It must be possible for implicit casts to cast it to a 64 bit unsigned integer.

C/C++ example:

```
void myfunc(uint64 myuint)
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )
```

F.1 Score-P User Adapter

```
SCOREP_USER_PARAMETER_UINT64("A nice unsigned int",myuint)

// do something

SCOREP_USER_REGION_END( my_region_handle )
}
```

F.1.2.26 #define SCOREP_USER_REGION(*name*, *type*)

Instruments a codeblock as a region with the given name. It inserts a local variable of the type class SCOREP_User_Region. Its constructor generates the enter event and its destructor generates the exit event. Thus, only one statement is necessary to instrument the code block. This statement is only in C++ available.

Parameters

<i>name</i>	A string containing the name of the new region. The name should be unique.
<i>type</i>	Specifies the type of the region. Possible values are SCOREP_USER_REGION_TYPE_COMMON, SCOREP_USER_REGION_TYPE_FUNCTION, SCOREP_USER_REGION_TYPE_LOOP, SCOREP_USER_REGION_TYPE_DYNAMIC, SCOREP_USER_REGION_TYPE_PHASE, or a combination of them.

Example:

```
void myfunc()
{
    SCOREP_USER_REGION_( "myfunc", SCOREP_USER_REGION_TYPE_FUNCTION )

    // do something
}
```

F.1.2.27 #define SCOREP_USER_REGION_BEGIN(*handle*, *name*, *type*)

Value:

```
SCOREP_User_RegionBegin( \
    &handle, &SCOREP_User_LastFileName, &SCOREP_User_LastFileHandle, name, \
    type, __FILE__, __LINE__ );
```

This macro marks the start of a user defined region. The SCOREP_USER_REGION_BEGIN and SCOREP_USER_REGION_END calls of all regions must be correctly nested.

APPENDIX F. MODULE DOCUMENTATION

Parameters

<i>handle</i>	The handle of the region to be started. This handle must be declared using SCOREP_USER_REGION_DEFINE or SCOREP_USER_GLOBAL_REGION_DEFINE before.
<i>name</i>	A string containing the name of the new region. The name should be unique.
<i>type</i>	Specifies the type of the region. Possible values are SCOREP_USER_REGION_TYPE_COMMON, SCOREP_USER_REGION_TYPE_FUNCTION, SCOREP_USER_REGION_TYPE_LOOP, SCOREP_USER_REGION_TYPE_DYNAMIC, SCOREP_USER_REGION_TYPE_PHASE, or a combination of them.

C/C++ example:

```
void myfunc()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // do something

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
        SCOREP_USER_REGION_TYPE_COMMON )

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    ! more declarations

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
        SCOREP_USER_REGION_TYPE_COMMON )
    ! do something
    SCOREP_USER_REGION_END( my_region_handle )

end program myProg
```

F.1.2.28 **#define SCOREP_USER_REGION_DEFINE(*handle*) static**
SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;

This macro defines a user region handle in a local context. Every user handle must be defined, before it can be used.

F.1 Score-P User Adapter

Parameters

<i>handle</i>	A unique name for the handle must be provided. This handle is declared in the macro. This handle is used in the SCOREP_USER_REGION_BEGIN and SCOREP_USER_REGION_END statements to specify which region is started, or ended. If you are using a Fortran version which has a limited length of code lines, the length of the <i>handle</i> parameter must be at most 4 characters, else the declaration line exceeds the allowed length.
---------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

C/C++ example:

```
void myfunc()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // do something

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    ! more declarations

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )
    ! do something
    SCOREP_USER_REGION_END( my_region_handle )

end program myProg
```

F.1.2.29 #define SCOREP_USER_REGION_END(*handle*) SCOREP_User.RegionEnd(*handle*);

This macro marks the end of a user defined region. The SCOREP_USER_REGION_BEGIN and SCOREP_USER_REGION_END calls of all regions must be correctly nested.

Parameters

<i>handle</i>	The handle of the region which ended here. It must be the same handle which is used as the start of the region.
---------------	-----------------------------------------------------------------------------------------------------------------

APPENDIX F. MODULE DOCUMENTATION

C/C++ example:

```
void myfunc()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // do something

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    ! more declarations

    SCOREP_USER_REGION_BEGIN( my_region_handle, "my_region",
    SCOREP_USER_REGION_TYPE_COMMON )
    ! do something
    SCOREP_USER_REGION_END( my_region_handle )

end program myProg
```

F.1.2.30 `#define SCOREP_USER_REGION_ENTER(handle) SCOREP_User_RegionEnter(
handle);`

This macro marks the beginning of a user defined and already initialized region. The SCOREP_USER_REGION_BEGIN/SCOREP_USER_REGION_ENTER and SCOREP_USER_REGION_END calls of all regions must be correctly nested. To initialize the region handle, [SCOREP_USER_REGION_INIT](#) or [SCOREP_USER_REGION_BEGIN](#) must be called before.

Parameters

<i>handle</i>	The handle of the region which ended here. It must be the same handle which is used as the start of the region.
---------------	-----------------------------------------------------------------------------------------------------------------

C/C++ example:

```
void myfunc()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )
```

F.1 Score-P User Adapter

```
// do something

SCOREP_USER_REGION_INIT( my_region_handle, "my_region",
SCOREP_USER_REGION_TYPE_COMMON )
SCOREP_USER_REGION_ENTER( my_region_handle )

// do something

SCOREP_USER_REGION_END( my_region_handle )
}
```

Fortran example:

```
program myProg
  SCOREP_USER_REGION_DEFINE( my_region_handle )
  ! more declarations

  SCOREP_USER_REGION_INIT( my_region_handle, "my_region",
SCOREP_USER_REGION_TYPE_COMMON )
  SCOREP_USER_REGION_ENTER( my_region_handle )
  ! do something
  SCOREP_USER_REGION_END( my_region_handle )

end program myProg
```

F.1.2.31 #define SCOREP_USER_REGION_INIT(*handle*, *name*, *type*)

Value:

```
SCOREP_User_RegionInit( \
    &handle, &SCOREP_User_LastFileName, &SCOREP_User_LastFileHandle, name, \
    type, __FILE__, __LINE__ );
```

This macro initializes a user defined region. If the region handle is already initialized, no operation is executed.

Parameters

<i>handle</i>	The handle of the region to be started. This handle must be declared using SCOREP_USER_REGION_DEFINE or SCOREP_USER_GLOBAL_REGION_DEFINE before.
<i>name</i>	A string containing the name of the new region. The name should be unique.
<i>type</i>	Specifies the type of the region. Possible values are SCOREP_USER_REGION_TYPE_COMMON, SCOREP_USER_REGION_TYPE_FUNCTION, SCOREP_USER_REGION_TYPE_LOOP, SCOREP_USER_REGION_TYPE_DYNAMIC, SCOREP_USER_REGION_TYPE_PHASE, or a combination of them.

APPENDIX F. MODULE DOCUMENTATION

C/C++ example:

```
void myfunc()
{
    SCOREP_USER_REGION_DEFINE( my_region_handle )

    // do something

    SCOREP_USER_REGION_INIT( my_region_handle, "my_region",
        SCOREP_USER_REGION_TYPE_COMMON )
    SCOREP_USER_REGION_ENTER( my_region_handle )

    // do something

    SCOREP_USER_REGION_END( my_region_handle )
}
```

Fortran example:

```
program myProg
    SCOREP_USER_REGION_DEFINE( my_region_handle )
    ! more declarations

    SCOREP_USER_REGION_INIT( my_region_handle, "my_region",
        SCOREP_USER_REGION_TYPE_COMMON )
    SCOREP_USER_REGION_ENTER( my_region_handle )
    ! do something
    SCOREP_USER_REGION_END( my_region_handle )

end program myProg
```

F.1.2.32 **#define SCOREP_USER_REGION_TYPE_COMMON 0**

Region without any specific type.

F.1.2.33 **#define SCOREP_USER_REGION_TYPE_DYNAMIC 4**

Marks the regions as dynamic.

F.1.2.34 **#define SCOREP_USER_REGION_TYPE_FUNCTION 1**

Marks the region as being the codeblock of a function.

F.1.2.35 **#define SCOREP_USER_REGION_TYPE_LOOP 2**

Marks the region as being the codeblock of a loop with the same number of iterations on all processes.

F.1 Score-P User Adapter

F.1.2.36 #define SCOREP_USER_REGION_TYPE_PHASE 8

Marks the region as being a root node of a phase.

Appendix G

File Documentation

G.1 SCOREP_User.h File Reference

This file contains the interface for the manual user instrumentation.

```
#include <scorep/SCOREP_User_Variables.h>
#include <scorep/SCOREP_User_Functions.h>
```

Defines

Macros for region instrumentation

- #define SCOREP_USER_FUNC_DEFINE()
- #define SCOREP_USER_OA_PHASE_BEGIN(handle, name, type)
- #define SCOREP_USER_OA_PHASE_END(handle) SCOREP_User_OaPhaseEnd(handle);
- #define SCOREP_USER_REGION_DEFINE(handle) static SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;
- #define SCOREP_USER_REGION_ENTER(handle) SCOREP_User_RegionEnter(handle);
- #define SCOREP_USER_REGION_BEGIN(handle, name, type)
- #define SCOREP_USER_REGION_INIT(handle, name, type)
- #define SCOREP_USER_REGION_END(handle) SCOREP_User_RegionEnd(handle);
- #define SCOREP_USER_FUNC_BEGIN()
- #define SCOREP_USER_FUNC_END() SCOREP_User_RegionEnd(scorep_user_func_handle);
- #define SCOREP_USER_GLOBAL_REGION_DEFINE(handle) SCOREP_User_RegionHandle handle = SCOREP_USER_INVALID_REGION;
- #define SCOREP_USER_GLOBAL_REGION_EXTERNAL(handle) extern SCOREP_User_RegionHandle handle;

Macros for parameter instrumentation

- #define `SCOREP_USER_PARAMETER_INT64`(name, value)
- #define `SCOREP_USER_PARAMETER_UINT64`(name, value)
- #define `SCOREP_USER_PARAMETER_STRING`(name, value)

Macros to provide user metrics

- #define `SCOREP_USER_METRIC_LOCAL`(metricHandle)
- #define `SCOREP_USER_METRIC_GLOBAL`(metricHandle)
- #define `SCOREP_USER_METRIC_EXTERNAL`(metricHandle) extern SCOREP_SamplingSetHandle metricHandle;
- #define `SCOREP_USER_METRIC_INIT`(metricHandle, name, unit, type, context) SCOREP_User_InitMetric(&metricHandle, name, unit, type, context);
- #define `SCOREP_USER_METRIC_INT64`(metricHandle, value)
- #define `SCOREP_USER_METRIC_UINT64`(metricHandle, value)
- #define `SCOREP_USER_METRIC_DOUBLE`(metricHandle, value)

C++ specific macros for region instrumentation

- #define `SCOREP_USER_REGION`(name, type)

Macros for measurement control

- #define `SCOREP_RECORDING_ON`() SCOREP_User_EnableRecording();
- #define `SCOREP_RECORDING_OFF`() SCOREP_User_DisableRecording();
- #define `SCOREP_RECORDING_IS_ON`() SCOREP_User_RecordingEnabled()

G.1.1 Detailed Description

This file contains the interface for the manual user instrumentation.

G.2 SCOREP_User_Types.h File Reference

This file contains type definitions for manual user instrumentation.

```
#include <scorep/SCOREP_PublicTypes.h>
```

Defines

- #define `SCOREP_USER_INVALID_PARAMETER` -1
- #define `SCOREP_USER_INVALID_REGION` NULL

G.2 SCOREP_User_Types.h File Reference

Region types

- `#define SCOREP_USER_REGION_TYPE_COMMON 0`
- `#define SCOREP_USER_REGION_TYPE_FUNCTION 1`
- `#define SCOREP_USER_REGION_TYPE_LOOP 2`
- `#define SCOREP_USER_REGION_TYPE_DYNAMIC 4`
- `#define SCOREP_USER_REGION_TYPE_PHASE 8`

Metric types

- `#define SCOREP_USER_METRIC_TYPE_INT64 0`
- `#define SCOREP_USER_METRIC_TYPE_UINT64 1`
- `#define SCOREP_USER_METRIC_TYPE_DOUBLE 2`

Metric contexts

- `#define SCOREP_USER_METRIC_CONTEXT_GLOBAL 0`
- `#define SCOREP_USER_METRIC_CONTEXT_CALLPATH 1`

Typedefs

- `typedef uint32_t SCOREP_User_MetricType`
- `typedef uint64_t SCOREP_User_ParameterHandle`
- `typedef struct SCOREP_User_Region * SCOREP_User_RegionHandle`
- `typedef uint32_t SCOREP_User_RegionType`

G.2.1 Detailed Description

This file contains type definitions for manual user instrumentation.

G.2.2 Define Documentation

G.2.2.1 `#define SCOREP_USER_INVALID_PARAMETER -1`

Marks an parameter handle as invalid or uninitialized

G.2.2.2 `#define SCOREP_USER_INVALID_REGION NULL`

Value for uninitialized or invalid region handles

G.2.3 Typedef Documentation

G.2.3.1 `typedef uint32_t SCOREP_User_MetricType`

Type for the user metric type

G.2.3.2 `typedef uint64_t SCOREP_User_ParameterHandle`

Type for parameter handles

G.2.3.3 `typedef struct SCOREP_User_Region* SCOREP_User_RegionHandle`

Type for region handles in the user adapter.

G.2.3.4 `typedef uint32_t SCOREP_User_RegionType`

Type for the region type

Index

Score-P User Adapter, [123](#)

SCOREP_RECORDING_IS_ON, [125](#)

SCOREP_RECORDING_OFF, [126](#)

SCOREP_RECORDING_ON, [126](#)

SCOREP_USER_FUNC_BEGIN, [127](#)

SCOREP_USER_FUNC_DEFINE, [128](#)

SCOREP_USER_FUNC_END, [129](#)

SCOREP_USER_GLOBAL_REGION_DEFINE, [129](#)

SCOREP_USER_GLOBAL_REGION_EXTERNAL, [130](#)

SCOREP_USER_METRIC_CONTEXT_CALLPATH, [132](#)

SCOREP_USER_METRIC_CONTEXT_GLOBAL, [132](#)

SCOREP_USER_METRIC_DOUBLE, [132](#)

SCOREP_USER_METRIC_EXTERNAL, [133](#)

SCOREP_USER_METRIC_GLOBAL, [134](#)

SCOREP_USER_METRIC_INIT, [135](#)

SCOREP_USER_METRIC_INT64, [136](#)

SCOREP_USER_METRIC_LOCAL, [137](#)

SCOREP_USER_METRIC_TYPE_DOUBLE, [138](#)

SCOREP_USER_METRIC_TYPE_INT64, [138](#)

SCOREP_USER_METRIC_TYPE_UINT64, [138](#)

SCOREP_USER_METRIC_UINT64, [139](#)

SCOREP_USER_OA_PHASE_BEGIN, [139](#)

SCOREP_USER_OA_PHASE_END, [141](#)

SCOREP_USER_PARAMETER_INT64, [142](#)

SCOREP_USER_PARAMETER_STRING, [143](#)

SCOREP_USER_PARAMETER_UINT64, [144](#)

SCOREP_USER_REGION, [145](#)

SCOREP_USER_REGION_BEGIN, [145](#)

SCOREP_USER_REGION_DEFINE, [146](#)

SCOREP_USER_REGION_END, [147](#)

SCOREP_USER_REGION_ENTER, [148](#)

SCOREP_USER_REGION_INIT, [149](#)

SCOREP_USER_REGION_TYPE_COMMON, [150](#)

SCOREP_USER_REGION_TYPE_DYNAMIC, [150](#)

SCOREP_USER_REGION_TYPE_FUNCTION, [150](#)

SCOREP_USER_REGION_TYPE_LOOP, [150](#)

SCOREP_USER_REGION_TYPE_PHASE, [150](#)

SCOREP_RECORDING_IS_ON

Score-P User Adapter, [125](#)

SCOREP_RECORDING_OFF

Score-P User Adapter, [126](#)

SCOREP_RECORDING_ON

Score-P User Adapter, [126](#)

SCOREP_User.h, [153](#)

SCOREP_USER_FUNC_BEGIN

Score-P User Adapter, [127](#)
 SCOREP_USER_FUNC_DEFINE
 Score-P User Adapter, [128](#)
 SCOREP_USER_FUNC_END
 Score-P User Adapter, [129](#)
 SCOREP_USER_GLOBAL_REGION_-
 DEFINE
 Score-P User Adapter, [129](#)
 SCOREP_USER_GLOBAL_REGION_-
 EXTERNAL
 Score-P User Adapter, [130](#)
 SCOREP_USER_INVALID_PARAMETER
 SCOREP_User_Types.h, [155](#)
 SCOREP_USER_INVALID_REGION
 SCOREP_User_Types.h, [155](#)
 SCOREP_USER_METRIC_CONTEXT_
 CALLPATH
 Score-P User Adapter, [132](#)
 SCOREP_USER_METRIC_CONTEXT_-
 GLOBAL
 Score-P User Adapter, [132](#)
 SCOREP_USER_METRIC_DOUBLE
 Score-P User Adapter, [132](#)
 SCOREP_USER_METRIC_EXTERNAL
 Score-P User Adapter, [133](#)
 SCOREP_USER_METRIC_GLOBAL
 Score-P User Adapter, [134](#)
 SCOREP_USER_METRIC_INIT
 Score-P User Adapter, [135](#)
 SCOREP_USER_METRIC_INT64
 Score-P User Adapter, [136](#)
 SCOREP_USER_METRIC_LOCAL
 Score-P User Adapter, [137](#)
 SCOREP_USER_METRIC_TYPE_DOUBLE
 Score-P User Adapter, [138](#)
 SCOREP_USER_METRIC_TYPE_INT64
 Score-P User Adapter, [138](#)
 SCOREP_USER_METRIC_TYPE_UINT64
 Score-P User Adapter, [138](#)
 SCOREP_USER_METRIC_UINT64
 Score-P User Adapter, [139](#)
 SCOREP_User_MetricType
 SCOREP_User_Types.h, [156](#)
 SCOREP_USER_OA_PHASE_BEGIN
 Score-P User Adapter, [139](#)
 SCOREP_USER_OA_PHASE_END
 Score-P User Adapter, [141](#)
 SCOREP_USER_PARAMETER_INT64
 Score-P User Adapter, [142](#)
 SCOREP_USER_PARAMETER_STRING
 Score-P User Adapter, [143](#)
 SCOREP_USER_PARAMETER_UINT64
 Score-P User Adapter, [144](#)
 SCOREP_User_ParameterHandle
 SCOREP_User_Types.h, [156](#)
 SCOREP_USER_REGION
 Score-P User Adapter, [145](#)
 SCOREP_USER_REGION_BEGIN
 Score-P User Adapter, [145](#)
 SCOREP_USER_REGION_DEFINE
 Score-P User Adapter, [146](#)
 SCOREP_USER_REGION_END
 Score-P User Adapter, [147](#)
 SCOREP_USER_REGION_ENTER
 Score-P User Adapter, [148](#)
 SCOREP_USER_REGION_INIT
 Score-P User Adapter, [149](#)
 SCOREP_USER_REGION_TYPE_COMMON
 Score-P User Adapter, [150](#)
 SCOREP_USER_REGION_TYPE_DYNAMIC
 Score-P User Adapter, [150](#)
 SCOREP_USER_REGION_TYPE_FUNCTION
 Score-P User Adapter, [150](#)
 SCOREP_USER_REGION_TYPE_LOOP
 Score-P User Adapter, [150](#)
 SCOREP_USER_REGION_TYPE_PHASE
 Score-P User Adapter, [150](#)
 SCOREP_User_RegionHandle
 SCOREP_User_Types.h, [156](#)
 SCOREP_User_RegionType
 SCOREP_User_Types.h, [156](#)
 SCOREP_User_Types.h, [154](#)
 SCOREP_USER_INVALID_PARAMETER,
 [155](#)
 SCOREP_USER_INVALID_REGION,
 [155](#)
 SCOREP_User_MetricType, [156](#)
 SCOREP_User_ParameterHandle, [156](#)

INDEX

SCOREP_User_RegionHandle, [156](#)

SCOREP_User_RegionType, [156](#)