

VOMS C API

1.5.0

Generated by Doxygen 1.7.1

Mon Oct 4 2010 14:08:21

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	attribute Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	5
3.1.2.1	name	5
3.1.2.2	qualifier	5
3.1.2.3	value	5
3.2	contactdata Struct Reference	6
3.2.1	Detailed Description	6
3.2.2	Field Documentation	6
3.2.2.1	contact	6
3.2.2.2	host	6
3.2.2.3	nick	6
3.2.2.4	port	6
3.2.2.5	reserved	6
3.2.2.6	version	7
3.2.2.7	vo	7
3.3	data Struct Reference	7
3.3.1	Detailed Description	7
3.3.2	Field Documentation	7
3.3.2.1	cap	7
3.3.2.2	group	7
3.3.2.3	role	8

3.4	voms Struct Reference	8
3.4.1	Detailed Description	8
3.4.2	Field Documentation	8
3.4.2.1	ac	8
3.4.2.2	custom	9
3.4.2.3	datalen	9
3.4.2.4	date1	9
3.4.2.5	date2	9
3.4.2.6	fqan	9
3.4.2.7	holder	9
3.4.2.8	serial	9
3.4.2.9	server	9
3.4.2.10	serverca	9
3.4.2.11	siglen	10
3.4.2.12	signature	10
3.4.2.13	std	10
3.4.2.14	type	10
3.4.2.15	uri	10
3.4.2.16	user	10
3.4.2.17	userca	10
3.4.2.18	version	10
3.4.2.19	voname	10
3.5	vomsdata Struct Reference	11
3.5.1	Detailed Description	11
3.5.2	Field Documentation	11
3.5.2.1	cdir	11
3.5.2.2	data	11
3.5.2.3	extra_data	11
3.5.2.4	extralen	11
3.5.2.5	real	12
3.5.2.6	vdir	12
3.5.2.7	volen	12
3.5.2.8	workvo	12
4	File Documentation	13
4.1	voms_apic.h File Reference	13
4.1.1	Define Documentation	15

4.1.1.1	RECURSE_CHAIN	15
4.1.1.2	RECURSE_NONE	15
4.1.1.3	TYPE_CUSTOM	15
4.1.1.4	TYPE_NODATA	15
4.1.1.5	TYPE_STD	16
4.1.1.6	VERIFY_CERTLIST	16
4.1.1.7	VERIFY_DATE	16
4.1.1.8	VERIFY_FULL	16
4.1.1.9	VERIFY_ID	16
4.1.1.10	VERIFY_KEY	16
4.1.1.11	VERIFY_NONE	16
4.1.1.12	VERIFY_NOTARGET	16
4.1.1.13	VERIFY_ORDER	16
4.1.1.14	VERIFY_SIGN	16
4.1.1.15	VERR_COMM	16
4.1.1.16	VERR_DIR	17
4.1.1.17	VERR_EXTRAINFO	17
4.1.1.18	VERR_FORMAT	17
4.1.1.19	VERR_IDCHECK	17
4.1.1.20	VERR_MEM	17
4.1.1.21	VERR_NODATA	17
4.1.1.22	VERR_NOEXT	17
4.1.1.23	VERR_NOIDENT	17
4.1.1.24	VERR_NOINIT	17
4.1.1.25	VERR_NONE	18
4.1.1.26	VERR_NOSOCKET	18
4.1.1.27	VERR_NOTAVAIL	18
4.1.1.28	VERR_ORDER	18
4.1.1.29	VERR_PARAM	18
4.1.1.30	VERR_PARSE	18
4.1.1.31	VERR_SERVER	18
4.1.1.32	VERR_SERVERCODE	18
4.1.1.33	VERR_SIGN	18
4.1.1.34	VERR_TIME	19
4.1.1.35	VERR_TYPE	19
4.1.1.36	VERR_VERIFY	19

4.1.2	Function Documentation	19
4.1.2.1	getMajorVersionNumber	19
4.1.2.2	getMinorVersionNumber	19
4.1.2.3	getPatchVersionNumber	19
4.1.2.4	VOMS_AddTarget	19
4.1.2.5	VOMS_Contact	19
4.1.2.6	VOMS_ContactRaw	20
4.1.2.7	VOMS_Copy	20
4.1.2.8	VOMS_CopyAll	21
4.1.2.9	VOMS_DefaultData	21
4.1.2.10	VOMS_Delete	21
4.1.2.11	VOMS_DeleteContacts	21
4.1.2.12	VOMS_Destroy	21
4.1.2.13	VOMS_Duplicate	22
4.1.2.14	VOMS_ErrorMessage	22
4.1.2.15	VOMS_Export	22
4.1.2.16	VOMS_FindByAlias	22
4.1.2.17	VOMS_FindByVO	23
4.1.2.18	VOMS_FreeTargets	23
4.1.2.19	VOMS_FreeTargetsList	24
4.1.2.20	VOMS_GetAC	24
4.1.2.21	VOMS_GetAttribute	24
4.1.2.22	VOMS_GetAttributeGrantor	24
4.1.2.23	VOMS_GetAttributesNumber	24
4.1.2.24	VOMS_GetAttributeSourceHandle	24
4.1.2.25	VOMS_GetAttributeSourcesNumber	24
4.1.2.26	VOMS_GetTargetsList	24
4.1.2.27	VOMS_Import	24
4.1.2.28	VOMS_Init	24
4.1.2.29	VOMS_ListTargets	25
4.1.2.30	VOMS_Ordering	25
4.1.2.31	VOMS_ResetOrder	25
4.1.2.32	VOMS_Retrieve	25
4.1.2.33	VOMS_RetrieveEXT	26
4.1.2.34	VOMS_RetrieveFromCred	26
4.1.2.35	VOMS_RetrieveFromCtx	26

4.1.2.36	VOMS_RetrieveFromFile	27
4.1.2.37	VOMS_RetrieveFromProxy	27
4.1.2.38	VOMS_SetLifetime	27
4.1.2.39	VOMS_SetTimeout	27
4.1.2.40	VOMS_SetVerificationTime	27
4.1.2.41	VOMS_SetVerificationType	27

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

attribute	5
contactdata	6
data (User's characteristics: can be repeated)	7
voms	8
vomsdata	11

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

voms_apic.h	13
-----------------------------	-------	----

Chapter 3

Data Structure Documentation

3.1 attribute Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- const char * [name](#)
- const char * [value](#)
- const char * [qualifier](#)

3.1.1 Detailed Description

Definition at line 53 of file voms_apic.h.

3.1.2 Field Documentation

3.1.2.1 const char* attribute::name

Definition at line 54 of file voms_apic.h.

3.1.2.2 const char* attribute::qualifier

Definition at line 56 of file voms_apic.h.

3.1.2.3 const char* attribute::value

Definition at line 55 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.2 contactdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- char * [nick](#)
- char * [host](#)
- char * [contact](#)
- char * [vo](#)
- int [port](#)
- char * [reserved](#)
- int [version](#)

3.2.1 Detailed Description

Definition at line 59 of file voms_apic.h.

3.2.2 Field Documentation

3.2.2.1 char* contactdata::contact

The subject of the server's certificate

Definition at line 64 of file voms_apic.h.

3.2.2.2 char* contactdata::host

The hostname of the server

Definition at line 63 of file voms_apic.h.

3.2.2.3 char* contactdata::nick

< You must never allocate directly this structure. Its sizeof() is subject to change without notice. The only supported way to obtain it is via the VOMS_FindBy* functions. The alias of the server

Definition at line 62 of file voms_apic.h.

3.2.2.4 int contactdata::port

The port on which the server is listening

Definition at line 66 of file voms_apic.h.

3.2.2.5 char* contactdata::reserved

HANDS OFF!

Definition at line 67 of file voms_apic.h.

3.2.2.6 int contactdata::version

The version of Globus on which this server runs.

Definition at line 68 of file voms_apic.h.

3.2.2.7 char* contactdata::vo

The VO served by this server

Definition at line 65 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.3 data Struct Reference

User's characteristics: can be repeated.

```
#include <voms_apic.h>
```

Data Fields

- char * [group](#)
- char * [role](#)
- char * [cap](#)

3.3.1 Detailed Description

User's characteristics: can be repeated. <

Definition at line 47 of file voms_apic.h.

3.3.2 Field Documentation

3.3.2.1 char* data::cap

user's capability

Definition at line 50 of file voms_apic.h.

3.3.2.2 char* data::group

user's group

Definition at line 48 of file voms_apic.h.

3.3.2.3 char* data::role

user's role

Definition at line 49 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.4 voms Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- int [siglen](#)
- char * [signature](#)
- char * [user](#)
- char * [userca](#)
- char * [server](#)
- char * [serverca](#)
- char * [voname](#)
- char * [uri](#)
- char * [date1](#)
- char * [date2](#)
- int [type](#)
- struct [data](#) ** [std](#)
- char * [custom](#)
- int [datalen](#)
- int [version](#)
- char ** [fqan](#)
- char * [serial](#)
- AC * [ac](#)
- X509 * [holder](#)

3.4.1 Detailed Description

Definition at line 79 of file voms_apic.h.

3.4.2 Field Documentation

3.4.2.1 AC* voms::ac

Definition at line 99 of file voms_apic.h.

3.4.2.2 char* voms::custom

The data returned by an S command

Definition at line 92 of file voms_apic.h.

3.4.2.3 int voms::datalen

Definition at line 93 of file voms_apic.h.

3.4.2.4 char* voms::date1

Beginning of validity of the user info

Definition at line 88 of file voms_apic.h.

3.4.2.5 char* voms::date2

End of validity of the user info

Definition at line 89 of file voms_apic.h.

3.4.2.6 char voms::fqan**

User's attributes in compact format

Definition at line 95 of file voms_apic.h.

3.4.2.7 X509* voms::holder

Definition at line 100 of file voms_apic.h.

3.4.2.8 char* voms::serial

Serial number. Only significant if coming from AC. Null otherwise

Definition at line 96 of file voms_apic.h.

3.4.2.9 char* voms::server

The VOMS server DN, as from its certificate

Definition at line 84 of file voms_apic.h.

3.4.2.10 char* voms::serverca

The CA which signed the VOMS certificate

Definition at line 85 of file voms_apic.h.

3.4.2.11 int voms::siglen

The length of the VOMS server signature

Definition at line 80 of file voms_apic.h.

3.4.2.12 char* voms::signature

The VOMS server signature

Definition at line 81 of file voms_apic.h.

3.4.2.13 struct data voms::std**

User's characteristics

Definition at line 91 of file voms_apic.h.

3.4.2.14 int voms::type

The type of data returned

Definition at line 90 of file voms_apic.h.

3.4.2.15 char* voms::uri

The URI of the VOMS server

Definition at line 87 of file voms_apic.h.

3.4.2.16 char* voms::user

The user's DN, as from his certificate

Definition at line 82 of file voms_apic.h.

3.4.2.17 char* voms::userca

The CA which signed the user's certificate

Definition at line 83 of file voms_apic.h.

3.4.2.18 int voms::version

Definition at line 94 of file voms_apic.h.

3.4.2.19 char* voms::vname

The name of the VO to which the VOMS belongs

Definition at line 86 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

3.5 vomsdata Struct Reference

```
#include <voms_apic.h>
```

Data Fields

- char * [cdir](#)
- char * [vdir](#)
- struct [voms](#) ** [data](#)
- char * [workvo](#)
- char * [extra_data](#)
- int [volen](#)
- int [extralen](#)
- struct [vomsdata](#) * [real](#)

3.5.1 Detailed Description

Definition at line 143 of file [voms_apic.h](#).

3.5.2 Field Documentation

3.5.2.1 char* vomsdata::cdir

Definition at line 144 of file [voms_apic.h](#).

3.5.2.2 struct voms** vomsdata::data

User's info, as in the certificate extension. It may contain data gathered from more than one VOMS server,

Definition at line 146 of file [voms_apic.h](#).

3.5.2.3 char* vomsdata::extra_data

The data specified by the user with the --include switch. Note that this field doesn't contain the result of a request to the VOMS server, but instead data specified by the user. The reason for the introduction of this extension is to let a user include important data into his proxy certificate, like, for example, a kerberos ticket

Definition at line 151 of file [voms_apic.h](#).

3.5.2.4 int vomsdata::extralen

Definition at line 161 of file [voms_apic.h](#).

3.5.2.5 struct vomsdata* vomsdata::real

Definition at line 163 of file voms_apic.h.

3.5.2.6 char* vomsdata::vdir

Definition at line 145 of file voms_apic.h.

3.5.2.7 int vomsdata::volen

Definition at line 160 of file voms_apic.h.

3.5.2.8 char* vomsdata::workvo

The value of the -vo option of the voms-proxy-init command

Definition at line 149 of file voms_apic.h.

The documentation for this struct was generated from the following file:

- [voms_apic.h](#)

Chapter 4

File Documentation

4.1 voms_apic.h File Reference

```
#include <gssapi.h>
#include <openssl/x509.h>
#include <time.h>
#include "newformat.h"
```

Data Structures

- struct [data](#)
User's characteristics: can be repeated.
- struct [attribute](#)
- struct [contactdata](#)
- struct [voms](#)
- struct [vomsdata](#)

Defines

- #define [TYPE_NODATA](#) 0
- #define [TYPE_STD](#) 1
- #define [TYPE_CUSTOM](#) 2
- #define [RECURSE_CHAIN](#) 0
- #define [RECURSE_NONE](#) 1
- #define [VERIFY_FULL](#) 0xffffffff
- #define [VERIFY_NONE](#) 0x00000000
- #define [VERIFY_DATE](#) 0x00000001
- #define [VERIFY_NOTARGET](#) 0x00000002
- #define [VERIFY_KEY](#) 0x00000004
- #define [VERIFY_SIGN](#) 0x00000008
- #define [VERIFY_ORDER](#) 0x00000010
- #define [VERIFY_ID](#) 0x00000020

- #define [VERIFY_CERTLIST](#) 0x00000040
- #define [VERR_NONE](#) 0

Error codes.

- #define [VERR_NOSOCKET](#) 1
- #define [VERR_NOIDENT](#) 2
- #define [VERR_COMM](#) 3
- #define [VERR_PARAM](#) 4
- #define [VERR_NOEXT](#) 5
- #define [VERR_NOINIT](#) 6
- #define [VERR_TIME](#) 7
- #define [VERR_IDCHECK](#) 8
- #define [VERR_EXTRAINFO](#) 9
- #define [VERR_FORMAT](#) 10
- #define [VERR_NODATA](#) 11
- #define [VERR_PARSE](#) 12
- #define [VERR_DIR](#) 13
- #define [VERR_SIGN](#) 14
- #define [VERR_SERVER](#) 15
- #define [VERR_MEM](#) 16
- #define [VERR_VERIFY](#) 17
- #define [VERR_TYPE](#) 18
- #define [VERR_ORDER](#) 19
- #define [VERR_SERVERCODE](#) 20
- #define [VERR_NOTAVAIL](#) 21

Functions

- struct [contactdata](#) ** [VOMS_FindByAlias](#) (struct [vomsdata](#) *vd, char *alias, char *system, char *user, int *error)
- struct [contactdata](#) ** [VOMS_FindByVO](#) (struct [vomsdata](#) *vd, char *vo, char *system, char *user, int *error)
- void [VOMS_DeleteContacts](#) (struct [contactdata](#) **list)
- struct [vomsdata](#) * [VOMS_Init](#) (char *voms, char *cert)
- struct [voms](#) * [VOMS_Copy](#) (struct [voms](#) *v, int *error)
- struct [vomsdata](#) * [VOMS_CopyAll](#) (struct [vomsdata](#) *vd, int *error)
- void [VOMS_Delete](#) (struct [voms](#) *v)
- int [VOMS_AddTarget](#) (struct [vomsdata](#) *vd, char *target, int *error)
- void [VOMS_FreeTargets](#) (struct [vomsdata](#) *vd, int *error)
- char * [VOMS_ListTargets](#) (struct [vomsdata](#) *vd, int *error)
- int [VOMS_SetVerificationType](#) (int type, struct [vomsdata](#) *vd, int *error)
- int [VOMS_SetLifetime](#) (int length, struct [vomsdata](#) *vd, int *error)
- void [VOMS_Destroy](#) (struct [vomsdata](#) *vd)
- int [VOMS_ResetOrder](#) (struct [vomsdata](#) *vd, int *error)
- int [VOMS_Ordering](#) (char *order, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Contact](#) (char *hostname, int port, char *servsubject, char *command, struct [vomsdata](#) *vd, int *error)
- int [VOMS_ContactRaw](#) (char *hostname, int port, char *servsubject, char *command, void **data, int *datalen, int *version, struct [vomsdata](#) *vd, int *error)

- int [VOMS_Retrieve](#) (X509 *cert, STACK_OF(X509)*chain, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Import](#) (char *buffer, int buflen, struct [vomsdata](#) *vd, int *error)
- int [VOMS_Export](#) (char **buffer, int *buflen, struct [vomsdata](#) *vd, int *error)
- struct [voms](#) * [VOMS_DefaultData](#) (struct [vomsdata](#) *vd, int *error)
- char * [VOMS_ErrorMessage](#) (struct [vomsdata](#) *vd, int error, char *buffer, int len)
- int [VOMS_RetrieveEXT](#) (X509_EXTENSION *ext, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromCred](#) (gss_cred_id_t cred, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromFile](#) (FILE *file, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromCtx](#) (gss_ctx_id_t ctx, int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_RetrieveFromProxy](#) (int how, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributeSourcesNumber](#) (struct [voms](#) *v, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributeSourceHandle](#) (struct [voms](#) *v, int num, struct [vomsdata](#) *vd, int *error)
- const char * [VOMS_GetAttributeGrantor](#) (struct [voms](#) *v, int handle, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttributesNumber](#) (struct [voms](#) *v, int handle, struct [vomsdata](#) *vd, int *error)
- int [VOMS_GetAttribute](#) (struct [voms](#) *v, int handle, int num, struct [attribute](#) *at, struct [vomsdata](#) *vd, int *error)
- struct [vomsdata](#) * [VOMS_Duplicate](#) (struct [vomsdata](#) *vd)
- AC * [VOMS_GetAC](#) (struct [voms](#) *v)
- int [getMajorVersionNumber](#) (void)
- int [getMinorVersionNumber](#) (void)
- int [getPatchVersionNumber](#) (void)
- int [VOMS_SetVerificationTime](#) (time_t verificationtime, struct [vomsdata](#) *vd, int *error)
- char ** [VOMS_GetTargetsList](#) (struct [voms](#) *v, struct [vomsdata](#) *vd, int *error)
- void [VOMS_FreeTargetsList](#) (char **)
- int [VOMS_SetTimeout](#) (int t, struct [vomsdata](#) *vd, int *error)

4.1.1 Define Documentation

4.1.1.1 #define RECURSE_CHAIN 0

Definition at line 104 of file voms_apic.h.

4.1.1.2 #define RECURSE_NONE 1

Definition at line 105 of file voms_apic.h.

4.1.1.3 #define TYPE_CUSTOM 2

result of an S command

Definition at line 76 of file voms_apic.h.

4.1.1.4 #define TYPE_NODATA 0

no data

Definition at line 74 of file voms_apic.h.

4.1.1.5 #define TYPE_STD 1

group, role, capability triplet

Definition at line 75 of file voms_apic.h.

4.1.1.6 #define VERIFY_CERTLIST 0x00000040

Definition at line 115 of file voms_apic.h.

4.1.1.7 #define VERIFY_DATE 0x00000001

Definition at line 109 of file voms_apic.h.

4.1.1.8 #define VERIFY_FULL 0xffffffff

Definition at line 107 of file voms_apic.h.

4.1.1.9 #define VERIFY_ID 0x00000020

Definition at line 114 of file voms_apic.h.

4.1.1.10 #define VERIFY_KEY 0x00000004

Definition at line 111 of file voms_apic.h.

4.1.1.11 #define VERIFY_NONE 0x00000000

Definition at line 108 of file voms_apic.h.

4.1.1.12 #define VERIFY_NOTARGET 0x00000002

Definition at line 110 of file voms_apic.h.

4.1.1.13 #define VERIFY_ORDER 0x00000010

Definition at line 113 of file voms_apic.h.

4.1.1.14 #define VERIFY_SIGN 0x00000008

Definition at line 112 of file voms_apic.h.

4.1.1.15 #define VERR_COMM 3

Server problem

Definition at line 122 of file voms_apic.h.

4.1.1.16 #define VERR_DIR 13

Directory error

Definition at line 133 of file voms_apic.h.

4.1.1.17 #define VERR_EXTRAINFO 9

VO name and URI missing

Definition at line 129 of file voms_apic.h.

4.1.1.18 #define VERR_FORMAT 10

Wrong data format

Definition at line 130 of file voms_apic.h.

4.1.1.19 #define VERR_IDCHECK 8

User data in extension different from the real ones

Definition at line 127 of file voms_apic.h.

4.1.1.20 #define VERR_MEM 16

Memory problems

Definition at line 136 of file voms_apic.h.

4.1.1.21 #define VERR_NODATA 11

Empty extension

Definition at line 131 of file voms_apic.h.

4.1.1.22 #define VERR_NOEXT 5

VOMS extension missing

Definition at line 124 of file voms_apic.h.

4.1.1.23 #define VERR_NOIDENT 2

Cannot identify itself (certificate problem)

Definition at line 121 of file voms_apic.h.

4.1.1.24 #define VERR_NOINIT 6

Initialization error

Definition at line 125 of file voms_apic.h.

4.1.1.25 #define VERR_NONE 0

Error codes.

Definition at line 119 of file voms_apic.h.

4.1.1.26 #define VERR_NOSOCKET 1

Socket problem

Definition at line 120 of file voms_apic.h.

4.1.1.27 #define VERR_NOTAVAIL 21

Method not available

Definition at line 141 of file voms_apic.h.

4.1.1.28 #define VERR_ORDER 19

Ordering different than required

Definition at line 139 of file voms_apic.h.

4.1.1.29 #define VERR_PARAM 4

Wrong parameters

Definition at line 123 of file voms_apic.h.

4.1.1.30 #define VERR_PARSE 12

Parse error

Definition at line 132 of file voms_apic.h.

4.1.1.31 #define VERR_SERVER 15

Unidentifiable VOMS server

Definition at line 135 of file voms_apic.h.

4.1.1.32 #define VERR_SERVERCODE 20

Error from the server

Definition at line 140 of file voms_apic.h.

4.1.1.33 #define VERR_SIGN 14

Signature error

Definition at line 134 of file voms_apic.h.

4.1.1.34 #define VERR_TIME 7

Error in time checking

Definition at line 126 of file voms_apic.h.

4.1.1.35 #define VERR_TYPE 18

Returned data of unknown type

Definition at line 138 of file voms_apic.h.

4.1.1.36 #define VERR_VERIFY 17

Generic verification error

Definition at line 137 of file voms_apic.h.

4.1.2 Function Documentation**4.1.2.1 int getMajorVersionNumber (void)****4.1.2.2 int getMinorVersionNumber (void)****4.1.2.3 int getPatchVersionNumber (void)****4.1.2.4 int VOMS_AddTarget (struct vomsdata * *vd*, char * *target*, int * *error*)**

Adds a target to the AC.

Parameters

vd The vomsdata structure.

target The target to add. It should be a FQDN.

error RETURN PARAMETER: qualifies the error message.

Returns

failure (0) or success (<>0)

4.1.2.5 int VOMS_Contact (char * *hostname*, int *port*, char * *servsubject*, char * *command*, struct vomsdata * *vd*, int * *error*)

Contacts a VOMS server to get a certificate

It is the equivalent of the voms_proxy_init command, but without the --include functionality.

Parameters

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command Command

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.6 `int VOMS_ContactRaw (char * hostname, int port, char * servsubject, char * command, void ** data, int * datalen, int * version, struct vomsdata * vd, int * error)`

The same as VOMS_Contact, except that instead of starting the verification process, the data is returned as is in the

Parameters

data and

datalen fields.

hostname FQDN of the VOMS server

port the port on which the VOMS server is listening

servsubject the subject of the server's certificate

command the command sent to the server

version is the version number of the data.

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.7 `struct voms* VOMS_Copy (struct voms * v, int * error) [read]`

Copies a voms structure. N.B: This is the ONLY way to correctly initialize a voms structure as a copy of another voms structure.

Parameters

v The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns

NULL (error) or the new voms structure.

4.1.2.8 struct vomsdata* VOMS_CopyAll (struct vomsdata * *vd*, int * *error*) [read]

Copies a vomsdata structure. N.B: This is the ONLY way to correctly initialize a vomsdata structure as a copy of another vomsdata structure.

Parameters

vd The structure to copy.

error RETURN PARAMETER: qualifies the error message.

Returns

NULL (error) or the new vomsdata structure.

4.1.2.9 struct voms* VOMS_DefaultData (struct vomsdata * *vd*, int * *error*) [read]

Gets the default attributes from a vomsdata structure.

Parameters

vd the vomsdata structure to analyze

error RETURN PARAMETER: Qualifies the error message

Returns

a pointer to the relevant voms structure. DO NOT modify the fields.

4.1.2.10 void VOMS_Delete (struct voms * *v*)

Deletes a voms structure

Parameters

v Pointer to the structure to delete.

4.1.2.11 void VOMS_DeleteContacts (struct contactdata ** *list*)

Frees a contactdata vector.

Parameters

list The vector to free.

Returns

NONE

4.1.2.12 void VOMS_Destroy (struct vomsdata * *vd*)

Destroys a proper vomsdata structure /param *vd* The structure to deallocate.

4.1.2.13 `struct vomsdata* VOMS_Duplicate (struct vomsdata * vd)` [**read**]

4.1.2.14 `char* VOMS_ErrorMessage (struct vomsdata * vd, int error, char * buffer, int len)`

Gets a textual description of the error.

Parameters

vd The vomsdata structure to analyze

error The error returned by the last function

buffer A pointer to a buffer where the error message will be written. If NULL, then memory is allocated by the function, and will have to be free()ed by the caller.

len The length of the memory pointed to by the buffer parameter.

Returns

A pointer to the error message.

4.1.2.15 `int VOMS_Export (char ** buffer, int * buflen, struct vomsdata * vd, int * error)`

Converts data into a test format

Parameters

buffer OUTPUT PARAMETER contains the converted data

buflen OUTPUT PARAMETER contains the length of buffer

vd contains the data to convert

error RETURN PARAMETER Qualifies the error message

Returns

failure (0) or success (>0)

4.1.2.16 `struct contactdata** VOMS_FindByAlias (struct vomsdata * vd, char * alias, char * system, char * user, int * error)` [**read**]

Gets a list of VOMS servers which share an alias.

Parameters

vd The correctly initialized vomsdata structured.

alias The alias to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/ed-c/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns

NULL, or a NULL-terminated vector of contactdata structures. The only supported way to free this array is via the VOMS_DeleteContacts function. Note also that the order in which the servers are returned is unspecified.

4.1.2.17 struct contactdata VOMS_FindByVO (struct vomsdata * *vd*, char * *vo*, char * *system*, char * *user*, int * *error*) [read]**

Gets a list of VOMS servers which serve the same VO.

Parameters

vd The correctly initialized vomsdata structured.

vo The VO to look for.

system The directory in which to look for the system configuration files. If NULL, defaults to /opt/edc/etc/vomses

user The directory in which to look for the user configuration files. Defaults to \$VOMS_USERCONF if NULL. Again defaults to \$HOME/.edg/vomses if the latter is NULL, or to ~/.edg/vomses as a last resort.

error RETURN PARAMETER: qualifies the error message.

Returns

NULL, or a NULL-terminated vector of contactdata structures. The only supported way to free this array is via the VOMS_DeleteContacts function. Note also that the order in which the servers are returned is unspecified.

4.1.2.18 void VOMS_FreeTargets (struct vomsdata * *vd*, int * *error*)

Delete the targets from the AC.

Parameters

vd The vomsdata structure.

error RETURN PARAMETER: qualifies the error message.

- 4.1.2.19** void VOMS_FreeTargetsList (char **)
- 4.1.2.20** AC* VOMS_GetAC (struct voms * v)
- 4.1.2.21** int VOMS_GetAttribute (struct voms * v, int *handle*, int *num*, struct attribute * *at*, struct vomsdata * *vd*, int * *error*)
- 4.1.2.22** const char* VOMS_GetAttributeGrantor (struct voms * v, int *handle*, struct vomsdata * *vd*, int * *error*)
- 4.1.2.23** int VOMS_GetAttributesNumber (struct voms * v, int *handle*, struct vomsdata * *vd*, int * *error*)
- 4.1.2.24** int VOMS_GetAttributeSourceHandle (struct voms * v, int *num*, struct vomsdata * *vd*, int * *error*)
- 4.1.2.25** int VOMS_GetAttributeSourcesNumber (struct voms * v, struct vomsdata * *vd*, int * *error*)
- 4.1.2.26** char** VOMS_GetTargetsList (struct voms * v, struct vomsdata * *vd*, int * *error*)
- 4.1.2.27** int VOMS_Import (char * *buffer*, int *buflen*, struct vomsdata * *vd*, int * *error*)

Converts data from the format used for inclusion into a certificate to the internal format

The function does verify the data.

Parameters

buffer contains the data to be converted

buflen contains the length of buffer

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

- 4.1.2.28** struct vomsdata* VOMS_Init (char * *voms*, char * *cert*) [read]

Initializes a vomsdata structure for use by the other functions. N.B: This is the ONLY way to correctly initialize a vomsdata structure. It is also forbidden to directly take the sizeof() of this structure.

Parameters

voms The directory which contains the certificates of the VOMS servers

cert The directory which contains the CA certificates

If voms_dir is empty, the value of the environment variable X509_VOMS_DIR is taken

If cert_dir is empty, the value of the environment variable X509_CERT_DIR is taken

Returns

NULL for failure, or a pointer to a properly initialized structure.

4.1.2.29 `char* VOMS_ListTargets (struct vomsdata * vd, int * error)`

4.1.2.30 `int VOMS_Ordering (char * order, struct vomsdata * vd, int * error)`

Further specified the order of the returned attributes. Please do note that calls are cumulative unless [VOMS_ResetOrder\(\)](#) is called.

Parameters

order the group:role attribute.

vd RETURN PARAMETER: contains the modified data.

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.31 `int VOMS_ResetOrder (struct vomsdata * vd, int * error)`

Unsets the return order of the attributes.

Parameters

vd RETURN PARAMETER: contains the modified data.

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.32 `int VOMS_Retrieve (X509 * cert, STACK_OF(X509)* chain, int how, struct vomsdata * vd, int * error)`

Extracts the VOMS extension from an X.509 certificate.

The function doesn't check the validity of the certificates, but it does check the content of the user data.

Parameters

cert The certificate with the VOMS extensions

chain The chain of the validation certificates (only the intermediate ones)

how Recursion type

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.33 int VOMS_RetrieveEXT (X509_EXTENSION * *ext*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given extension

Parameters

ext The extension to parse.

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.34 int VOMS_RetrieveFromCred (gss_cred_id_t *cred*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus credential

Parameters

cred The credential from which to retrieve the certificate.

how Recursion type

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.35 int VOMS_RetrieveFromCtx (gss_ctx_id_t *ctx*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus context

Parameters

ctx The context from which to retrieve the certificate.

how Recursion type

vd RETURN PARAMETER: contains the data returned by the connection

error RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.36 int VOMS_RetrieveFromFile (FILE * *file*, int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from the given globus credential

Parameters

- file* The file from which to retrieve the certificate.
- how* Recursion type
- vd* RETURN PARAMETER: contains the data returned by the connection
- error* RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.37 int VOMS_RetrieveFromProxy (int *how*, struct vomsdata * *vd*, int * *error*)

Gets VOMS information from an existing globus proxy

Parameters

- how* Recursion type
- vd* RETURN PARAMETER: contains the data returned by the connection
- error* RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.38 int VOMS_SetLifetime (int *length*, struct vomsdata * *vd*, int * *error*)

Set requested lifetime for [VOMS_Contact\(\)](#) calls.

Parameters

- length* Lifetime requested.
- vd* RETURN PARAMETER: contains the modified data.
- error* RETURN PARAMETER: Qualifies the error message

Returns

failure (0) or success (<>0)

4.1.2.39 int VOMS_SetTimeout (int *t*, struct vomsdata * *vd*, int * *error*)**4.1.2.40 int VOMS_SetVerificationTime (time_t *verificationtime*, struct vomsdata * *vd*, int * *error*)****4.1.2.41 int VOMS_SetVerificationType (int *type*, struct vomsdata * *vd*, int * *error*)**

Index

- ac
 - voms, 8
- attribute, 5
 - name, 5
 - qualifier, 5
 - value, 5
- cap
 - data, 7
- cdir
 - vomsdata, 11
- contact
 - contactdata, 6
- contactdata, 6
 - contact, 6
 - host, 6
 - nick, 6
 - port, 6
 - reserved, 6
 - version, 6
 - vo, 7
- custom
 - voms, 8
- data, 7
 - cap, 7
 - group, 7
 - role, 7
 - vomsdata, 11
- datalen
 - voms, 9
- date1
 - voms, 9
- date2
 - voms, 9
- extra_data
 - vomsdata, 11
- extralen
 - vomsdata, 11
- fqan
 - voms, 9
- getMajorVersionNumber
 - voms_apic.h, 19
- getMinorVersionNumber
 - voms_apic.h, 19
- getPatchVersionNumber
 - voms_apic.h, 19
- group
 - data, 7
- holder
 - voms, 9
- host
 - contactdata, 6
- name
 - attribute, 5
- nick
 - contactdata, 6
- port
 - contactdata, 6
- qualifier
 - attribute, 5
- real
 - vomsdata, 11
- RECURSE_CHAIN
 - voms_apic.h, 15
- RECURSE_NONE
 - voms_apic.h, 15
- reserved
 - contactdata, 6
- role
 - data, 7
- serial
 - voms, 9
- server
 - voms, 9
- serverca
 - voms, 9
- siglen
 - voms, 9
- signature
 - voms, 10
- std
 - voms, 10

- type
 - voms, [10](#)
- TYPE_CUSTOM
 - voms_apic.h, [15](#)
- TYPE_NODATA
 - voms_apic.h, [15](#)
- TYPE_STD
 - voms_apic.h, [15](#)
- uri
 - voms, [10](#)
- user
 - voms, [10](#)
- userca
 - voms, [10](#)
- value
 - attribute, [5](#)
- vdir
 - vomsdata, [12](#)
- VERIFY_CERTLIST
 - voms_apic.h, [16](#)
- VERIFY_DATE
 - voms_apic.h, [16](#)
- VERIFY_FULL
 - voms_apic.h, [16](#)
- VERIFY_ID
 - voms_apic.h, [16](#)
- VERIFY_KEY
 - voms_apic.h, [16](#)
- VERIFY_NONE
 - voms_apic.h, [16](#)
- VERIFY_NOTARGET
 - voms_apic.h, [16](#)
- VERIFY_ORDER
 - voms_apic.h, [16](#)
- VERIFY_SIGN
 - voms_apic.h, [16](#)
- VERR_COMM
 - voms_apic.h, [16](#)
- VERR_DIR
 - voms_apic.h, [16](#)
- VERR_EXTRAINFO
 - voms_apic.h, [17](#)
- VERR_FORMAT
 - voms_apic.h, [17](#)
- VERR_IDCHECK
 - voms_apic.h, [17](#)
- VERR_MEM
 - voms_apic.h, [17](#)
- VERR_NODATA
 - voms_apic.h, [17](#)
- VERR_NOEXT
 - voms_apic.h, [17](#)
- VERR_NOIDENT
 - voms_apic.h, [17](#)
- VERR_NOINIT
 - voms_apic.h, [17](#)
- VERR_NONE
 - voms_apic.h, [17](#)
- VERR_NOSOCKET
 - voms_apic.h, [18](#)
- VERR_NOTAVAIL
 - voms_apic.h, [18](#)
- VERR_ORDER
 - voms_apic.h, [18](#)
- VERR_PARAM
 - voms_apic.h, [18](#)
- VERR_PARSE
 - voms_apic.h, [18](#)
- VERR_SERVER
 - voms_apic.h, [18](#)
- VERR_SERVERCODE
 - voms_apic.h, [18](#)
- VERR_SIGN
 - voms_apic.h, [18](#)
- VERR_TIME
 - voms_apic.h, [18](#)
- VERR_TYPE
 - voms_apic.h, [19](#)
- VERR_VERIFY
 - voms_apic.h, [19](#)
- version
 - contactdata, [6](#)
 - voms, [10](#)
- vo
 - contactdata, [7](#)
- volen
 - vomsdata, [12](#)
- voms, [8](#)
 - ac, [8](#)
 - custom, [8](#)
 - datalen, [9](#)
 - date1, [9](#)
 - date2, [9](#)
 - fqan, [9](#)
 - holder, [9](#)
 - serial, [9](#)
 - server, [9](#)
 - serverca, [9](#)
 - siglen, [9](#)
 - signature, [10](#)
 - std, [10](#)
 - type, [10](#)
 - uri, [10](#)
 - user, [10](#)
 - userca, [10](#)
 - version, [10](#)

- voname, 10
- VOMS_AddTarget
 - voms_apic.h, 19
- voms_apic.h, 13
 - getMajorVersionNumber, 19
 - getMinorVersionNumber, 19
 - getPatchVersionNumber, 19
 - RECURSE_CHAIN, 15
 - RECURSE_NONE, 15
 - TYPE_CUSTOM, 15
 - TYPE_NODATA, 15
 - TYPE_STD, 15
 - VERIFY_CERTLIST, 16
 - VERIFY_DATE, 16
 - VERIFY_FULL, 16
 - VERIFY_ID, 16
 - VERIFY_KEY, 16
 - VERIFY_NONE, 16
 - VERIFY_NOTARGET, 16
 - VERIFY_ORDER, 16
 - VERIFY_SIGN, 16
 - VERR_COMM, 16
 - VERR_DIR, 16
 - VERR_EXTRAINFO, 17
 - VERR_FORMAT, 17
 - VERR_IDCHECK, 17
 - VERR_MEM, 17
 - VERR_NODATA, 17
 - VERR_NOEXT, 17
 - VERR_NOIDENT, 17
 - VERR_NOINIT, 17
 - VERR_NONE, 17
 - VERR_NOSOCKET, 18
 - VERR_NOTAVAIL, 18
 - VERR_ORDER, 18
 - VERR_PARAM, 18
 - VERR_PARSE, 18
 - VERR_SERVER, 18
 - VERR_SERVERCODE, 18
 - VERR_SIGN, 18
 - VERR_TIME, 18
 - VERR_TYPE, 19
 - VERR_VERIFY, 19
 - VOMS_AddTarget, 19
 - VOMS_Contact, 19
 - VOMS_ContactRaw, 20
 - VOMS_Copy, 20
 - VOMS_CopyAll, 20
 - VOMS_DefaultData, 21
 - VOMS_Delete, 21
 - VOMS_DeleteContacts, 21
 - VOMS_Destroy, 21
 - VOMS_Duplicate, 21
 - VOMS_ErrorMessage, 22
 - VOMS_Export, 22
 - VOMS_FindByAlias, 22
 - VOMS_FindByVO, 22
 - VOMS_FreeTargets, 23
 - VOMS_FreeTargetsList, 23
 - VOMS_GetAC, 24
 - VOMS_GetAttribute, 24
 - VOMS_GetAttributeGrantor, 24
 - VOMS_GetAttributesNumber, 24
 - VOMS_GetAttributeSourceHandle, 24
 - VOMS_GetAttributeSourcesNumber, 24
 - VOMS_GetTargetsList, 24
 - VOMS_Import, 24
 - VOMS_Init, 24
 - VOMS_ListTargets, 24
 - VOMS_Ordering, 25
 - VOMS_ResetOrder, 25
 - VOMS_Retrieve, 25
 - VOMS_RetrieveEXT, 25
 - VOMS_RetrieveFromCred, 26
 - VOMS_RetrieveFromCtx, 26
 - VOMS_RetrieveFromFile, 26
 - VOMS_RetrieveFromProxy, 27
 - VOMS_SetLifetime, 27
 - VOMS_SetTimeout, 27
 - VOMS_SetVerificationTime, 27
 - VOMS_SetVerificationType, 27
 - VOMS_Contact
 - voms_apic.h, 19
 - VOMS_ContactRaw
 - voms_apic.h, 20
 - VOMS_Copy
 - voms_apic.h, 20
 - VOMS_CopyAll
 - voms_apic.h, 20
 - VOMS_DefaultData
 - voms_apic.h, 21
 - VOMS_Delete
 - voms_apic.h, 21
 - VOMS_DeleteContacts
 - voms_apic.h, 21
 - VOMS_Destroy
 - voms_apic.h, 21
 - VOMS_Duplicate
 - voms_apic.h, 21
 - VOMS_ErrorMessage
 - voms_apic.h, 22
 - VOMS_Export
 - voms_apic.h, 22
 - VOMS_FindByAlias
 - voms_apic.h, 22
 - VOMS_FindByVO
 - voms_apic.h, 22
 - VOMS_FreeTargets

voms_apic.h, [23](#)
VOMS_FreeTargetsList
voms_apic.h, [23](#)
VOMS_GetAC
voms_apic.h, [24](#)
VOMS_GetAttribute
voms_apic.h, [24](#)
VOMS_GetAttributeGrantor
voms_apic.h, [24](#)
VOMS_GetAttributesNumber
voms_apic.h, [24](#)
VOMS_GetAttributeSourceHandle
voms_apic.h, [24](#)
VOMS_GetAttributeSourcesNumber
voms_apic.h, [24](#)
VOMS_GetTargetsList
voms_apic.h, [24](#)
VOMS_Import
voms_apic.h, [24](#)
VOMS_Init
voms_apic.h, [24](#)
VOMS_ListTargets
voms_apic.h, [24](#)
VOMS_Ordering
voms_apic.h, [25](#)
VOMS_ResetOrder
voms_apic.h, [25](#)
VOMS_Retrieve
voms_apic.h, [25](#)
VOMS_RetrieveEXT
voms_apic.h, [25](#)
VOMS_RetrieveFromCred
voms_apic.h, [26](#)
VOMS_RetrieveFromCtx
voms_apic.h, [26](#)
VOMS_RetrieveFromFile
voms_apic.h, [26](#)
VOMS_RetrieveFromProxy
voms_apic.h, [27](#)
VOMS_SetLifetime
voms_apic.h, [27](#)
VOMS_SetTimeout
voms_apic.h, [27](#)
VOMS_SetVerificationTime
voms_apic.h, [27](#)
VOMS_SetVerificationType
voms_apic.h, [27](#)
vomsdata, [11](#)
 cdir, [11](#)
 data, [11](#)
 extra_data, [11](#)
 extralen, [11](#)
 real, [11](#)
 vdir, [12](#)
 volen, [12](#)
 workvo, [12](#)
voname
 voms, [10](#)
workvo
 vomsdata, [12](#)