

Geometric Tools Engine Version 3.2 Installation Manual and Release Notes

David Eberly, [Geometric Tools](#)

Document Version 3.2

July 6, 2016

Contents

| | | |
|----------|--|-----------|
| 1 | Introduction | 3 |
| 1.1 | License | 3 |
| 1.2 | Copying the Distribution to Your Machine | 4 |
| 2 | Development on Microsoft Windows | 5 |
| 2.1 | Environment Variables | 5 |
| 2.2 | Compiling the Source Code | 5 |
| 2.3 | Support for OpenGL | 6 |
| 2.4 | Automatic Generation of Project and Solution Files | 6 |
| 2.5 | Running the Samples | 6 |
| 2.6 | Microsoft Visual Studio Custom Visualizers | 7 |
| 2.7 | Falling Back to Direct3D 10 | 7 |
| 2.8 | Falling Back to Direct3D 9 | 8 |
| 2.9 | No Support Yet for Dynamic Libraries for GTEngine | 8 |
| 3 | Development on Linux | 8 |
| 3.1 | Environment Variables | 8 |
| 3.2 | Dependencies on Other Packages | 9 |
| 3.3 | Compiling the Source Code | 9 |
| 3.4 | Support for OpenGL via Proprietary Drivers | 9 |
| 3.5 | Running the Samples | 10 |
| 4 | Development on Macintosh OS X | 10 |

| | | |
|----------|---|-----------|
| 5 | Accessing the OpenGL Driver Information | 10 |
| 6 | Automatic Generation of a Wrapper for OpenGL | 11 |

1 Introduction

You are about to install Geometric Tools Engine 3.2. Version 1.0 source code was the companion to the book [GPGPU Programming for Games and Science](#) and was developed on Microsoft Windows 8.1 using Microsoft Visual Studio 2013, C++ 11, and Direct3D 11.1. Version 3.x is close enough to what is in the book that you should have no problem navigating the code as you read the book. The source code has been reorganized using subfolders of Source and Include, and the header includes are now slightly different.

Version 3.x has a graphics engine that requires minimally OpenGL 4.3 (or later) and GLSL 4.3 (or later) in order to support compute shaders and GLSL introspection, and it runs on both Microsoft Windows (WGL) and Linux (GLX). **Please observe that the engine and sample applications require OpenGL 4.3 (or later) and GLSL 4.3 (or later).** If your graphics driver does not support this, the applications will gracefully terminate with a message to the console window: *OpenGL 4.3 is required*. In particular, the Nouveau Open Source graphics drivers that ship with the various flavors of Linux do not currently support OpenGL 4.3 (or later) or GLSL 4.3 (or later). You must install the graphics card manufacturer's proprietary driver.

Visit the [Geometric Tools](#) website for updates, bug fixes, known problems, new features, and other materials.

1.1 License

The Geometric Tools Engine uses the [Boost License](#), listed next.

Boost Software License - Version 1.0 - August 17th, 2003

Permission is hereby granted, free of charge, to any person or organization obtaining a copy of the software and accompanying documentation covered by this license (the Software) to use, reproduce, display, distribute, execute, and transmit the Software, and to prepare derivative works of the Software, and to permit third-parties to whom the Software is furnished to do so, all subject to the following:

The copyright notices in the Software and this entire statement, including the above license grant, this restriction and the following disclaimer, must be included in all copies of the Software, in whole or in part, and all derivative works of the Software, unless such copies or derivative works are solely in the form of machine-executable object code generated by a source language processor.

THE SOFTWARE IS PROVIDED ‘‘AS IS’’, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR ANYONE DISTRIBUTING THE SOFTWARE BE LIABLE FOR ANY DAMAGES OR OTHER LIABILITY, WHETHER IN CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

1.2 Copying the Distribution to Your Machine

You may unzip the distribution to a folder of your choice. The top-level folder of the distribution is GeometricTools and the subfolder for the distribution is named GTEngine. Some of the folder hierarchy is shown next. The Include and Source folders contain all the code for the engine.

```
GeometricTools
GTEngine
  Include
    Applications
      GLX
      MSW
      DX11
      WGL
    Graphics
      DX11
      GL4
      GLX
      WGL
    Imagics
    LowLevel
    MSW
    Mathematics
    MSW
    Physics
  Source
    Applications
      GLX
      MSW
      DX11
      WGL
    Graphics
      DX11
      GL4
      GLX
      WGL
    Imagics
    LowLevel
    MSW
    Mathematics
    MSW
    Physics
  Samples
    Data
    Basics
    Geometrics
    Graphics
    Imagics
    Mathematics
    Physics
    DX11
  Shaders
  Tools
    BitmapFontCreator
    GenerateApproximations
    GenerateOpenGLWrapper
    GenerateProject
```

```
// Root folder for Geometric Tools Engine, set GTE_PATH to here.
// Location for *.h files.
// Platform-independent classes.
// Support for Linux GLX applications.
// Support for Microsoft Windows applications.
// Support for Direct3D 11 applications.
// Support for WGL applications.
// Platform-independent graphics files.
// DX11-specific graphics files.
// Platform-independent OpenGL-specific graphics files.
// Linux GLX graphics files.
// WGL graphics files.
// Image processing files.
// Several low-level utility files.
// Microsoft Windows-specific files.
// The bulk of the engine consists of mathematics support.
// Microsoft Windows-specific files.
// Some physics support, not all WM5 physics code has been ported.
// Location for *.cpp files.
// Platform-independent classes.
// Support for Linux GLX applications.
// Support for Microsoft Windows applications.
// Support for Direct3D 11 applications.
// Support for WGL applications.
// Platform-independent graphics files.
// DX11-specific graphics files.
// Platform-independent OpenGL-specific graphics files.
// Linux GLX graphics files.
// WGL graphics files.
// Image processing files.
// Several low-level utility files.
// Microsoft Windows-specific files.
// The bulk of the engine consists of mathematics support.
// Microsoft Windows-specific files.
// Some physics support, not all WM5 physics code has been ported.
// Sample applications, many discussed in the GPGPU book.
// A small number of data files for the samples.
// Basic tutorials for several HLSL concepts.
// Samples for computational geometry.
// Samples for graphics and video streams (parallel copy).
// Samples for 2D and 3D image processing.
// Samples for mathematical algorithms and numerical methods.
// Samples for 2D and 3D physics.
// Samples specifically for Direct3D 11.
// HLSL/GLSL shader files (embedded versions are in the engine source).
// Several convenient tools.
// Generate .h/.cpp file to represent a graphics font.
// Used to generate the minimax approximations for common functions.
// Source-code generator for gl* wrappers driven by glcorearb.h.
// Generate MSVS 2013/2015 vcxproj, sln, h, and cpp for applications.
```


The Samples subfolders are many. Listing them here would make the displayed hierarchy difficult to read. The projects all use paths relative to GTEngine and they do not rely on the top-level directory being located at the root of a hard drive. An environment variable GTE_PATH is used to locate data files required by the application. How you set an environment variable depends on the operating system and/or shell you are using.

2 Development on Microsoft Windows

The code is maintained currently on an Intel-based computer with Microsoft Windows 10, Version 1511 (OS Build 10.586.420). If you develop on Microsoft Windows 7 or 8.x and encounter problems with the code, contact us via the email address listed at the [Geometric Tools](#) website.

2.1 Environment Variables

Create an environment variable named `GTE_PATH` that stores the absolute directory path to the folder `GeometricTools/GTEngine`. For example, if you unzipped the distribution to the root of the C drive, you would set `GTE_PATH` to `C:/GeometricTools/GTEngine`. You can set environment variables via `System | Advanced system settings`, which launches the `System Properties` dialog with a button for `Environment Variables`.



2.2 Compiling the Source Code

Microsoft Visual Studio 2013 uses Version 12 of the compiler and Microsoft Visual Studio 2015 uses Version 14 of the compiler. The project and solution names have embedded in them v12 or v14; that is, both versions of the compiler are supported. The engine solutions are `GeometricTools/GTEngine/GTEngine.v12.sln` and `GeometricTools/GTEngine/GTEngine.v14.sln`. Each sample application or tool has its own solution with all dependencies listed, so it is possible to open a sample application and compile and run it without

explicitly building the engine solution first. The folder `GTEngine` contains the solutions `GTBuildAll.v12.sln` and `GTBuildAll.v14.sln` if you want to build the engine, samples, and tools at the same time rather than building the projects separately.

2.3 Support for OpenGL

All the Microsoft Visual Studio projects have configurations `Debug` and `Release` that include compiling the `Direct3D 11` source code. The configurations `DebugGL4` and `ReleaseGL4` include compiling the `OpenGL` source code. Although it is possible to have an application that creates both a `Direct3D 11` engine and an `OpenGL` engine, the current project design does not allow this. If you have such a need, you must create your own `GTEngine` project that enables both sets of graphics code. For example, you might have an application that uses `OpenGL` for rendering but uses `Direct3D 11` for compute shaders (for `GPGPU`).

2.4 Automatic Generation of Project and Solution Files

Creating a new Microsoft Visual Studio project and manually setting its properties to match those of the current sample applications is tedious. A tool is provided to generate a skeleton project, solution, and source files, `GeometricTools/GTEngine/Tools/GenerateProject`. As an example of how to use the tool, suppose you want to create a new project in the folder, `GeometricTools/GTEngine/Samples/Graphics/MySample` for a sample application. Copy `GenerateProject.exe` to that folder, and in a command window opened in that folder, execute

```
GenerateProject 3 MySample
```

The number 3 indicates the nesting of the `MySample` folder relative to the `GTEngine` folder. The tool creates the files `MySample.v12.sln`, `MySample.v12.vcxproj`, `MySample.v12.vcxproj.filters`, `MySample.v14.sln`, `MySample.v14.vcxproj`, `MySample.v14.vcxproj.filters`, `MySampleWindow.h`, and `MySampleWindow.cpp`. You can open the solution, build, and run to see a blank window of size 512×512 . The copyright notice generated as the preamble of the files `MySampleWindow.*` is for our convenience—you may delete those notices.

If you want the generated files to live in a folder outside the `GTEngine` hierarchy, you will need to modify the include path in the projects to `$(GTE_PATH)/Include`. You will also need to delete the `GTEngine` project from the `Required` folder of the solution and re-add it so that the correct path occurs. This is necessary because the Microsoft Visual Studio reference system is used to link in the `GTEngine` library.

Also, it is not necessary to copy `GenerateProject.exe` to the project folder. If the executable can be found via the `PATH` statement, just execute it in any folder of your choosing and then copy the generated files to your project folder.

2.5 Running the Samples

You can run the samples from within the Microsoft Visual Studio development environment. Samples that access data files use the `GTE_PATH` environment variable to locate those files; code is in place to assert when the environment variable is not set. If you run from Microsoft Windows, presumably double-clicking an executable via Windows Explorer, the environment variable is still necessary.

Many of the samples compile HLSL shaders at run time. This requires having `D3Dcompiler.*.dll` in your path, where `*` is the version number of the shader compiler. You might have to modify your `PATH` environment variable to include the path. With latest Windows, the DLL should be in a Windows Kit bin folder.

2.6 Microsoft Visual Studio Custom Visualizers

A new file has been added, `GeometricTools/GTEngine/gtengine.natvis`, that provides a native visualizer for the `Vector` and `Matrix` classes. Copy this to `C:/Users/YOURLOGIN/Documents/Visual Studio 2015/Visualizers`. More visualizers will be added over time. Feel free to suggest GTEngine classes for which you want specialized visualization during debugging.

2.7 Falling Back to Direct3D 10

For Microsoft Windows machines, the default settings for GTEngine are to use Direct3D 11.0 or later for rendering and to compile the shaders for the built-in effects (such as `Texture2Effect` and `VertexColorEffect`) using Shader Model 5. These settings are also used when compiling shaders that are part of the sample application or those you write yourself. If you do not have graphics hardware recent enough to support the default configuration, it is possible to modify the start-up code in the sample applications to fall back to Direct3D 10.0 (Shader Model 4.0) or Direct3D 10.1 (Shader Model 4.1).

Open the graphics sample named `VertexColoring`. The main function has the block of code

```
Window::Parameters parameters(L"VertexColoringWindow", 0, 0, 512, 512);
auto window = TheWindowSystem.Create<VertexColoringWindow>(parameters);
TheWindowSystem.MessagePump(window, TheWindowSystem.DEFAULT_ACTION);
TheWindowSystem.Destroy<VertexColoringWindow>(window);
```

All the 2D and 3D windowed applications have similar blocks of code. The `Window::Parameters` structure has a member named `featureLevel` that defaults to `D3D_FEATURE_LEVEL_11_0`. The general list of values from which you can choose is

```
enum D3D_FEATURE_LEVEL
{
    D3D_FEATURE_LEVEL_9_1 = 0x9100, // 4_0_level_9_1
    D3D_FEATURE_LEVEL_9_2 = 0x9200, // 4_0_level_9_1
    D3D_FEATURE_LEVEL_9_3 = 0x9300, // 4_0_level_9_3
    D3D_FEATURE_LEVEL_10_0 = 0xa000, // 4_0
    D3D_FEATURE_LEVEL_10_1 = 0xa100, // 4_1
    D3D_FEATURE_LEVEL_11_0 = 0xb000, // 5_0
    D3D_FEATURE_LEVEL_11_1 = 0xb100, // 5_1
}
D3D_FEATURE_LEVEL;
```

The enumeration is found in `d3dcommon.h`. If you have a graphics card that supports at most Direct3D 10.0, then modify the main code to

```
Window::Parameters parameters(L"VertexColoringWindow", 0, 0, 512, 512);
#if !defined(GTE_DEV_OPENGL)
    parameters.featureLevel = D3D_FEATURE_LEVEL_10_0;
    HLSLProgramFactory::defaultVersion = "4_0";
#endif
auto window = TheWindowSystem.Create<VertexColoringWindow>(parameters);
TheWindowSystem.MessagePump(window, TheWindowSystem.DEFAULT_ACTION);
TheWindowSystem.Destroy<VertexColoringWindow>(window);
```

Comments were added after the enumerates to indicate what to assign to `HLSLProgramFactory::defaultVersion`. For non-windowed applications, the `DX11Engine` constructors allow you to specify directly the feature level.

2.8 Falling Back to Direct3D 9

This is not really possible, because `GTEngine` uses constant buffers and other concepts without equivalent DX9 representations. The best you can do is specify one of the feature levels mentioned in the previous section for which `LEVEL_9` is part of the name. Note that there is no shader profile with name `4.0.level_9.2`. If you set the version string to “3_0”, the `D3DReflect` call will fail with `HRESULT 0x8876086C`, which is not listed in `winerror.h`. This is the code for the obsolete `D3DERR_INVALIDCALL`. The HLSL assembly instructions for Shader Model 3 do not contain constant buffer register assignments (because they did not exist then).

2.9 No Support Yet for Dynamic Libraries for GTEngine

Currently, the engine solution generates static libraries. The hooks are in place for dynamic libraries, but the build configurations have not yet been added to the projects.

3 Development on Linux

The `GTEngine` source code and sample applications have been tested on three flavors of Linux: [Fedora 24](#), [Debian 8.5.0](#), and [Ubuntu 16.04](#). As mentioned previously, your graphics driver must be capable of OpenGL 4.3 (or later) and GLSL 4.3 (or later).

If you have obtained `GTEngine 3.2` as a package already part of the Linux distribution, all you need do is set an environment variable and compile the sample applications. The `GTEngine` libraries should already be built, and the headers and libraries should be installed in the default locations. The other directions provided here are for those obtaining the package from the [Geometric Tools](#) website.

3.1 Environment Variables

Create an environment variable named `GTE_PATH` that stores the absolute directory path to the folder `GeometricTools/GTEngine`. For example, if you use a bash shell, you would define the environment variable in the file `.bashrc` by adding the line

```
GTE_PATH=/home/YOURLOGIN/GeometricTools/GTEngine ; export GTE_PATH
```

The actual path depends on `YOURLOGIN` and where you copied the `GTEngine` distribution. The `.bashrc` file is processed when you login; however, if you modify it after logging in, you may process it by executing

```
source .bashrc
```

from a terminal window whose active directory is your home folder. For other versions of Linux or other shells, consult your user’s guide on how to create an environment variable.

3.2 Dependencies on Other Packages

Each of the three supported flavors of Linux was installed from Live distributions. GTEngine depends on development packages for X11, OpenGL, GLX, and libpng. The latter package is used for a simple reader/writer of PNG files for the sample applications. The package manager for Fedora 24 is `dnf` and the package manager for Debian 8.5.0 and Ubuntu 16.04 is `apt`. The names of the dependent packages vary with Linux distribution.

3.3 Compiling the Source Code

The makefile to build the GTEngine library is `GeometricTools/GTEngine/makeengine.gte` where both static and shared library builds are supported. From a terminal window execute

```
make CFG=configuration -f makeengine.gte
```

where `configuration` is `Debug` or `Release` for static libraries and `DebugDynamic` or `ReleaseDynamic` for shared libraries.

You can build all samples by changing directory to `GeometricTools/GTEngine/Samples` and executing

```
make CFG=configuration -f makeallsamples.gte
```

If you want to build a single sample application, change directory to the sample folder. For example, change directory to `GeometricTools/GTEngine/Samples/Graphics/VertexColoring` and execute

```
make CFG=configuration APP=VertexColoring -f ../../makesample.gte
```

3.4 Support for OpenGL via Proprietary Drivers

On Fedora 24 and Ubuntu 16.04, `glxinfo` showed that the Nouveau drivers are OpenGL 4.1. On Debian 8.5.0, the Nouveau driver is OpenGL 3.3. In all cases, you cannot run the sample applications with the Nouveau drivers—you need the proprietary drivers.

Installing the NVIDIA proprietary driver (version 367.27) was challenging. This version of the driver supports OpenGL 4.5. The installation directions varied for each Linux OS. After searching the Internet, the following links led to successful installation. The directions are not for the most recent versions of the operating systems, but the directions still apply.

- [Install on Fedora 24](#)
- [Install on Debian 8.5.0](#)
- [Install on Ubuntu 16.04](#)

The Ubuntu directions are via a search using Google, and there is a simple summary of steps listed at the top of the search page.

The bare minimum of GLX functions is used to create windows that allow OpenGL accelerated rendering. All functions are included in the GLX packages for Linux, so there is no need for GLX extensions.

3.5 Running the Samples

For the static library builds, you can simply open a terminal window and change directory to the project directory. For example, if you built the static release library and the `Graphics/BlendedTerrain` sample application, the application can be launched by executing `./BlendedTerrain.Release`

For shared library builds, the libraries are stored in `GeometricTools/GTEngine/lib`. Once GTEngine 3.2 becomes part of the Linux distributions, you will find these libraries in the standard locations. Before then, a simple way to launch the application is the following. Suppose you have a terminal window open and you have changed directory to `Samples/Graphics/BlendedTerrain` and that you have built the shared release versions of the engine and application. Execute the following

```
LD_LIBRARY_PATH=$GTE_PATH/lib/ReleaseDynamic ./BlendedTerrain.Release
```

4 Development on Macintosh OS X

Support for graphics on the Macintosh has been discontinued because compute shaders and GLSL introspection require OpenGL 4.3 (or later) but Apple has not updated their OpenGL support from version 4.1. However, the nongraphics and nonapplication code compiles. An Xcode project (actually a folder and subfolders) is provided, `GeometricTools/GTEngine/GTEngine.xcodeproj`, that allows you to build any of four configurations. The `Debug` and `Release` configurations generate static libraries. The `Debug Dynamic` and `Release Dynamic` configurations generate shared libraries.

With the introduction of Mac OS X 10.7, access to environment variables via the library function `getenv` appears to have been disabled. A `plist` mechanism used to work with earlier versions of the operating system, but no longer. The Wild Magic 5 distribution had a workaround for this, but the sample applications in GTEngine are not supported on the Macintosh, so there is no need for the workaround.

5 Accessing the OpenGL Driver Information

This section is applicable both to Microsoft Windows and to Linux.

The `GL4Engine` code is designed to allow you to write to disk information about the OpenGL driver. Extending the example for `VertexColoring` described in the previous sections, modify the `main` code

```
Window::Parameters parameters(L"VertexColoringWindow", 0, 0, 512, 512);
#if defined(GTE_DEV_OPENGL)
    parameters.deviceCreationFlags = 1;
#endif
auto window = TheWindowSystem.Create<VertexColoringWindow>(parameters);
TheWindowSystem.MessagePump(window, TheWindowSystem.DEFAULT_ACTION);
TheWindowSystem.Destroy<VertexColoringWindow>(window);
```

For now the only device creation flags for OpenGL are the default 0 or 1, the latter causing the OpenGL driver information to be written to a file named `OpenGLDriverInfo.txt`. The first several lines of the file show the vendor, the renderer (graphics card model and related), and the OpenGL version supported by the driver. The remaining lines list supported OpenGL extensions.

6 Automatic Generation of a Wrapper for OpenGL

Several packages may be found online that provide wrappers that query for OpenGL function pointers and that encapsulate many of the gory details in using the OpenGL API. As an alternative, GTEngine ships with a tool to build a wrapper, `GeometricTools/GTEngine/Tools/GenerateOpenGLWrapper`. The file `GteOpenGL.h` was written manually—do not modify it. The file `GteOpenGL.cpp` is generated by parsing `glcorearb.h`, a file that is available from the [OpenGL Registry](#). This file is introduced in the OpenGL 4.3 Specification.

If the file is updated, or if you want to use a previous version, you can copy your file to the tool's project folder and then use the wrapper tool to regenerate `GteOpenGL.cpp` and copy it to

```
GeometricTools/GTEngine/Source/Graphics/GL4/GteOpenGL.cpp
```

You must also copy your version of `glcorearb.h` to

```
GeometricTools/GTEngine/Include/Graphics/GL4/GL/glcorearb.h
```

The extension files from the OpenGL Registry were also copied to the same folder as `glcorearb.h`. These include `glxext.h`, `glxext.h`, and `wglxext.h`. The first three are not used by the engine, but the last one is used by the WGL OpenGL engine.

The `GenerateOpenGLWrapper` tool has projects for Microsoft Visual Studio. To build this on Linux,

```
g++ -std=c++14 -c GenerateOpenGLWrapper.c -o GenerateOpenGLWrapper.o
g++ GenerateOpenGLWrapper.o -o GenerateOpenGLWrapper
```

and then execute the program in the project folder.